

Feb 09, 2023

Version 1

TaME-seq2 V.1

Forked from a private protocol

DOI

<https://dx.doi.org/10.17504/protocols.io.dm6gpjxy5gzp/v1>

jean-marc¹, Milan Stosic², Alexander Hesselberg^{1,2}, trinro³

¹Akershus University Hospital; ²Oslo Metropolitan University; ³University of Oslo



Alexander Hesselberg

Norwegian Institute of Public Health

Create & collaborate more with a free account

Edit and publish protocols, collaborate in communities, share insights through comments, and track progress with run records.

Create free account

OPEN  ACCESS



DOI: <https://dx.doi.org/10.17504/protocols.io.dm6gpjxy5gzp/v1>

Protocol Citation: jean-marc , Milan Stosic, Alexander Hesselberg, trinro 2023. TaME-seq2. **protocols.io**
<https://dx.doi.org/10.17504/protocols.io.dm6gpjxy5gzp/v1>

Manuscript citation:

TaME-seq2: Tagmentation-assisted multiplex PCR enrichment sequencing for viral genomic profiling. Alexander Hesselberg Løvestad, Milan S. Stosic, Jean-Marc Costanzi, Irene Kraus Christiansen, Hege Vangstein Aamot, Ole Herman Ambur, Trine B. Rounge *Viral J* **20**, 44 (2023). <https://doi.org/10.1186/s12985-023-02002-5>

License: This is an open access protocol distributed under the terms of the **Creative Commons Attribution License**, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working

We use this protocol and it's working

Created: February 02, 2023

Last Modified: February 09, 2023

Protocol Integer ID: 76285

Keywords: integration, library preparation, illumina, virus, viral integrations, snp, snps, variants, whole genome sequencing, genome, genomics, enrichment, multiplex PCR, multiplex pcr enrichment, assisted multiplex pcr enrichment, viral genomic profiling, multiplex pcr reaction of tagmented dna, viral genome, multiplex pcr reaction, extracted dna, illumina dna prep kit, tagmented dna, integration enrichment library preparation protocol, seq2 tagmentation, transcribed cdna, sequencing, pcr, tagmentation of sample, using purification bead

Abstract

Tagmentation-assisted multiplex PCR enrichment sequencing for viral genomic profiling (TaME-seq2). Viral genome and integration enrichment library preparation protocol.

Manuscript:

TaME-seq2: Tagmentation-assisted multiplex PCR enrichment sequencing for viral genomic profiling.

Alexander Hesselberg Løvestad, Milan S. Stosic, Jean-Marc Costanzi, Irene Kraus Christiansen, Hege Vangstein Aamot, Ole Herman Ambur, Trine B. Rounge medRxiv 2022.12.22.22283851

doi: <https://doi.org/10.1101/2022.12.22.22283851>

Before starting:

Prepare samples consisting of extracted DNA or reverse transcribed cDNA.

The method consists of three main parts:

Part 1:

Tagmentation of samples using the Illumina DNA Prep kit.

Part 2:

Multiplex PCR reaction of tagmented DNA/cDNA, using virus-specific primers and i5/i7 indexes.

Part 3:

Clean-up and size selection using purification beads/Ampure XP beads.



Materials

	A	B	C
	Component	Supplier	Catalog number
	Illumina® DNA Prep, (M) Tagmentation (96 Samples)	Illumina	20018705
	QIAGEN Multiplex PCR Kit (100)	Qiagen	206143
	AMPure XP 60 mL	Beckman Coulter	A63881

Sample preparation

- 1 Prepare and normalize DNA/cDNA samples by measuring sample concentration and diluting in nuclease-free water if necessary.

Sample volume should be  15 µL

 50 ng input is recommended, but the protocol works with less and performance is more dependent on viral load.

Tagmentation

- 2 Prepare a master mix for the tagmentation reaction and add sample DNA and master mix to individual wells.

	A	B	C
Reagent	1x	10x	
Bead linked transposoms (BLT)	5 µL	50 µL	
Tagmentation buffer 1 (TB1)	5 µL	50 µL	
Sample DNA/cDNA	15 µL		
Total	25 µL	10×10 µL	

Tagmentation reagent mix table

Note

You should prepare 10% extra to account for loss during pipetting

- 3 Incubate the samples as follows:

15m



00:15:00 at 55 °C

Hold at 4 °C

Note

Let it cool down to 4 °C before taking it out of the thermocycler.

- 4 Add 5 µL of Tagmentation stop buffer (TSB) to each sample.

Note

The Tagmentation stop buffer needs to be vortexed well before use.

- 5 Incubate sample for 00:15:00 at 37 °C

15m

Note

The samples can be stored in the fridge for a few hours after this step.

- 6 Wash the samples

9m

1. Place tubes on the magnetic rack for 00:03:00 (or until solution is clear)
2. Discard supernatant
3. Remove tube from magnetic rack and add 50 µL Tagment wash buffer (TWB) and mix to resuspend beads
4. Place tubes on magnetic rack for 00:03:00 and remove supernatant
5. Repeat step 3 and 4 for a total of 2 washes
6. Add 50 µL TWB to samples and mix
7. Close cap on tubes and place on magnet. Allow to incubate for at least 00:03:00 and continue the protocol. The samples will be used later in the PCR

Note

The samples are submerged in TWB to stop the beads from overdrying while working on the next steps.

The samples can also be eluted in  14 µL nuclease-free water and stored in the freezer, if so do not add H2O/elution buffer to the PCR master mix in the next step.

Amplification of tagmented DNA

7

20m

1. Make the PCR master mix

	A	B	C
Reagent	1x	10x	
2x PCR master mix	12,5 µl	125 µl	
Q-solution x5	2,5 µl	25 µl	
Primer pool (15 µM)	1 µl		
i5/i7 indexes (10 µM)	2 µl		
Nuclease-free water	7 µl	70 µl	
Total	25 µl	22 µL x 10 µL + 3 µL primers per sample	

Note

One master mix need to be prepared for each of the forward and reverse primer pools.

Nuclease-free water, primer pool and i5/i7 indexes will be dispensed in each individual well in the downstream PCR 96-well plate.

If samples were eluted in nuclease-free water after step 6, add  7 μL of the eluted sample to the individual wells instead of nuclease-free water.

2. Remove supernatant from samples prepared in step 6.7 and remove from magnetic rack
3. Add  30 μL of PCR MM to the samples, mix well and resuspend the beads (the beads can be difficult to resuspend, but they don't need to be completely resuspended)
4. Pipette  15 μL out of the sample to a new well containing the nuclease-free water, primer pool and i5/i7 indexes, for separate F and R reactions
5. Run the touchdown PCR reaction using the following program on the thermal cycler:

Step	Temperature	Time	Cycles
Initial denaturation	 95 °C	 00:05:00	1
<i>Touchdown PCR:</i>			
Denaturation	 95 °C	 00:00:30	10
Annealing	 68 °C -  58 °C	 00:01:30	10 (decrease  1 °C per cycle)
Extension	 72 °C	 00:00:30	10
<i>PCR:</i>			
Denaturation	 95 °C	 00:00:30	26
Annealing	 58 °C	 00:01:30	26
Extension	 72 °C	 00:00:30	26
Final extension	 68 °C	 00:10:00	26
Hold	 4 °C		

**Note**

We use a touchdown PCR as this gives the best amplification yield for us. This, and other PCR parameters, might differ between primer pools.

If amplification yield is low, consider changing the ramping temperature.

Clean up and size selection, pooling and quality control

5m

- 8
- 1) After the PCR reaction is finished place the plate on the magnet for 00:05:00
 - 2) Transfer 20 μL of the supernatant to a fresh well (transfer less than the total volume to compensate for differences in volume during pipetting).
 - 3) Pool 10 μL of each sample in an eppendorf tubes.
 - 4) Vortex and invert purification beads (PB) to fully resuspend.
 - 5) Prepare a master mix of diluted PB (Note: The volumes used in the master mix is for each sample that has been pooled).

	A	B
	Reagent	Volume per reaction
	PB	10 μL
	Nuclease-free water	8,85 μL

- 6) Vortex and mix the diluted master mix and add 18.75 μL (per reaction) master mix to the pool and **mix well**

Note

The mixing is essential for a good size selection and increasing yield

- 7) Seal the tubes and incubate at room temperature for 00:05:00
- 8) Place on magnet for 00:05:00 5 min or until clear
- 9) Add 3.7 μL (per reaction) of PB to a new eppendorf tube
- 10) Transfer 27 μL (per reaction) of the supernatant to the eppendorf tube containing PB and **mix well**

Note

The mixing is essential for a good size selection and increasing yield

- 11) Seal the tube and incubate at room temperature for  00:05:00
- 12) Place the tube on a magnet for  00:05:00 or until clear
- 13) Remove and discard the supernatant without disrupting the beads
- 14) With the tube on the magnet, add fresh 80% ethanol to cover the beads without mixing and incubate  00:01:00
- 15) Remove the ethanol
- 16) Repeat steps 14 and 15 for a total of 2 washes
- 17) Remove any excess liquid from the tube
- 18) Air-dry on the magnet for  00:05:00 or until dry. The bead should not dry so long that it cracks while ethanol residues should have evaporated.
- 19) Remove the tube from the magnet and add  205 μL (more or less depending on desired reaction volume to elute in) resuspension buffer/water-free nuclease to the beads and mix
- 20) Incubate at room temperature for  00:05:00
- 21) Place tube on magnet for  00:02:00 or until clear
- 22) Transfer  200 μL of the supernatant into a fresh tube
- 23) Clean up two more times (start from step 12) using 0,65x ratio Ampure beads, elute in  42 μL and transfer  40 μL to a new tube before assessing size distribution again.

9

Assess the quality of the pools using a Bioanalyzer or an equivalent instrument to see the fragment size distribution.

If there is an excess of small fragments in the library, clean up one or more times (start from step 11) using 0,65x ratio Ampure beads, elute in  42 μL and transfer  40 μL to a new tube before assessing size distribution again.