AUG 12, 2019

🌐 DNA extraction from sputum

Laszlo Irinyi¹, Lana Pasic², Wieland Meyer²

¹Westmead Institute for Medical Research; ²The University of Sydney

Laszlo Irinyi

Westmead Institute for Medical Research, The University of S...

OPEN ACCESS

DOI:

dx.doi.org/10.17504/protocols.io.6enhbde

Protocol Citation: Laszlo Irinyi, Lana Pasic, Wieland Meyer 2019. DNA extraction from sputum. **protocols.io** <https://dx.doi.org/10.17504/protocols.io.6enhbde>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
We use this protocol and it's working

Created: Aug 12, 2019

Last Modified: Aug 12, 2019

PROTOCOL integer ID:
26798

Breaking the cells with liquid nitrogen

- 1 The sputum samples were transferred to 1.5ml Eppendorf tubes for liquid nitrogen cell wall breakage, with a maximum of 600 µl of sputum per tube. Under full PPE conditions, the lid of the tube was left open, and a small plastic pestle placed to sit inside. Liquid nitrogen was transferred

10m

into a 100 ml cup. The tube, with the pestle inside, was placed into the liquid nitrogen, up until the lid opening, for three seconds. Once removed, the pestle was used to ground up and crush the sputum inside, turning it continuously for 60 seconds, and the process was repeated five times for each tube.

Following the manufacturer's instructions of Sputum DNA I...

- 2** Add 4 mL of Slurry D for every 1 mL of sputum sample in a 15 mL conical tube. Mix well by inversion. (Note: Slurry D contains silicon carbide resin and must be mixed well before every pipeting). 2m
- 3** Centrifuge for 5 minutes at 2,000 RPM. Discard the supernatant. 5m
- 4** Add 20 μ L of both Proteinase K and Lysozyme (user supplied) to the precipitated slurry pellet resulting from the sputum sample. Vortex for 10 seconds. 10s
- 5** Incubate the mixture at 60°C for 20 minutes. 20m
- 6** After the 20 minute incubation, add 260 μ L Solution WN, and mix well by pipetting up and down. 1m
- 7** Transfer the entire contents into a Mini Filter Spin column (provided) with collection tube. 1h
- 8** Centrifuge for 1 minute at 14,000 RPM, and discard the flow-through. 1m

- 9** Apply 500 μ L of Wash Solution BE to the column and centrifuge for 1 minute. Discard the flowthrough and reassemble the spin column with its collection tube. 1m
- 10** Apply 500 μ L of Wash Solution BE to the column and centrifuge for 1 minute. Discard the flow-through and reassemble the spin column with its collection tube. 1m
- 11** Apply 500 μ L of 96-100% Ethanol (user supplied) to the column and centrifuge for 1 minute. Discard the flow-through and reassemble the spin column with its collection tube. 1m
- 12** Spin the column for 2 minutes in order to thoroughly dry the resin. Discard the collection tube. 2m
- 13** Transfer the spin column to a fresh 1.7 mL Elution tube. Apply 100 μ L of Nuclease free water to the column and centrifuge for 2 minutes at 2,000 RPM, followed by 1 minute at 14,000 RPM. 2m
- 14** The DNA concentration of the samples is determined using DeNovix dsDNA Broad Range Fluorescent Assay Kit (Denovix, Wilmington, USA) 10m