OCT 06, 2020

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.bm2ek8be

Protocol Citation: Christopher Neil Thornton, William Brazelton 2020. DNA Extraction from Sterivex Filters. **protocols.io** <https://dx.doi.org/10.17504/protocols.io.bm2ek8be>

MANUSCRIPT CITATION:
 Lever et al. (2015) doi: 10.3389/fmicb.2015.00476.

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
 We use this protocol and it's working

Created: Oct 05, 2020

Last Modified: Oct 06, 2020

PROTOCOL integer ID:
 42790

DNA Extraction from Sterivex Filters

Christopher Neil Thornton¹, William Brazelton¹

¹University of Utah

Gigascience Database
 GigaScience

DISCLAIMER

DISCLAIMER – FOR INFORMATIONAL PURPOSES ONLY; USE AT YOUR OWN RISK

The protocol content here is for informational purposes only and does not constitute legal, medical, clinical, or safety advice, or otherwise; content added to [protocols.io](#) is not peer reviewed and may not have undergone a formal approval of any kind. Information presented in this protocol should not substitute for independent professional judgment, advice, diagnosis, or treatment. Any action you take or refrain from taking using or relying upon the information presented here is strictly at your own risk. You agree that neither the Company nor any of the authors, contributors, administrators, or anyone else associated with [protocols.io](#), can be held responsible for your use of the information contained in or linked to this protocol or any of our Sites/Apps and Services.

ABSTRACT

Modified 2015 by the Brazelton Lab from protocols by Rika Anderson, Colleen Kellogg, Julie Huber, and Byron Crump. Incorporated some recommendations from Lever et al. (2015) *Frontiers in Microbiology* doi: 10.3389/fmicb.2015.00476.

Hot Lysis

- 1 Add 1.4 mL of DEB to each Sterivex with syringe and needle. Position the needle just below the mouth of the Sterivex so that it does not come back out the top. Do not fill to the top – stop when solution covers white filter. Possible Stopping Point. Store at 20°C
 - 1.1 Possible Stopping Point. Store at 20°C
- 2 Place sterivex filter in 50mL tube with holes.
- 3 Incubate at 65°C for 30 mins. on Genemate spinning machine.
- 4 Vortex each sterivex again (inside the Falcon tube) for 30 seconds. Bead Beating:

Bead Beating

- 5 Using a syringe, withdraw fluid from each Sterivex and eject into bead tube (glass 0.1 mm for bacteria).
- 6 Bead beat for 40 s.
- 7 Centrifuge for 2 min at 5000 g.

- 8 Add equal volume of phenol / chloroform / isoamyl alcohol (25:24:1, bought premixed with alkaline buffer) to each tube.

Phenol/Chloroform extraction

- 9 Transfer fluid avoiding beads into fresh Eppendorf tube. Add no more than 900 μ L in each tube (or no more than 750 μ L if using 1.5 mL tubes). Phenol / chloroform extraction:
- 10 Gently shake a few times and then centrifuge at 14,000g for 1 minute.
- 11 Remove supernatant to fresh tube.
- 12 Add equal volume of chloroform / isoamyl alcohol (24:1) to each tube.
- 13 Gently shake a few times and centrifuge.
- 14 Remove supernatant to fresh tube, carefully avoiding the bottom organic layer. Ethanol precipitation:

Ethanol precipitation

- 15** Redistribute aqueous phase among 3 tubes so that each 2.0 mL tube has 550 μ L or less and each 1.6 mL tube has 450 μ L or less. For some samples, additional salt is not necessary, and you can skip the sodium acetate. In this case, you can add up to 600 μ L in a 2.0 mL tube.
- 16** Add 0.1 volumes sodium acetate (3M, pH 5.2). (e.g. add 55 μ L to 550 μ L.)
- 17** Add 2 volumes 100% ethanol. (e.g. add 1210 μ L to 605 μ L.)
- 18** [optional for low biomass samples] Add 1.2 μ L of glycogen (20 μ g/ μ L).
- 19** Invert a few times to mix.
- 20** Incubate at 20°C for at least 1 hr. or overnight. Incubation on ice might work just as well and yield a cleaner pellet.
- 21** Centrifuge for 40 minutes at 16,000g. (Optional: used cooled centrifuge at 0°C)
- 22** Pour out supernatant. Do not completely invert tube; keep at a gentle angle to minimize the chance of the pellet falling out.
- 23** Add 500 μ L of cold 70% ethanol to each tube.

- 24 Invert the tube to mix. Make sure the pellet is dislodged from the bottom so that it is properly washed.
- 25 Centrifuge at 16,000g for 10 minutes.
- 26 Remove liquid again with pipettor. Be careful to avoid pellet.
- 27 Place tubes with open lids in the Vacufuge. Spin for 7 minutes at 30°C on the VAL setting. If you can see ethanol in the tube, spin for another 25 minutes. If the pellets become powdery, they are too dry.
- 28 Resuspend in ~100 µL of low EDTA TE. Heat to 55°C

Note

Recipe for low EDTA TE: 10 mM TrisHCl 0.1 mM EDTA For 50 ml: 500 µl 1 M TrisHCl (pH 8.0) autoclaved 10 µl 0.5 M EDTA (pH 8.0) autoclaved → to 50 ml with milliQ H₂O → filter sterilize with 0.22 µm syringe filter TE is good for DNA storage, but EDTA inhibits PCR. So this low EDTA TE buffer is a good compromise for storing DNA for later PCR amplification. You can also just use EB (10 mM TrisHCl, pH 8 or 8.5).

for 10 or more minutes to dissolve pellet and store at 4°C. For longterm storage, place at 20 or-80°C, but avoid repeated freezing and thawing of the DNA. One strategy is to keep half at 4°C for the working sample and store the other half at 80°C as the archive sample.