OCT 14, 2019

E. coli Colony PCR

Igem Dusseldorf¹

¹Heinrich-Heine Universität Düsseldorf

Igem Dusseldorf

ABSTRACT

Ideally use at least two master mixes:

2 vector-specific primers (to determine insert size):

1 vector-specific + 1 gene-specific primer

To save resources one of them could be enough. Is not as neat as it should be but functional. Use Vector + gene specific, because then you can be sure, that the gene is inserted in the right direction

For genotyping of putative colonies

Prepare a PCR master mix for 9 reactions, as follows:

	1x Reaction (Volume; µL)	9x Reactions (Volume; µL)
Sterile MilliQ Water	8	72
Red Taq 2x Master Mix (1.5 mM MgCl ₂)	10	90
F Primer (10 µM)	1	9
R Primer (10 µM)	1	9
Total Volume	20	180

- Aliquot 20 µL of the master mix in the 8 tubes of a PCR strip.

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.76ihrce

Protocol Citation: Igem Dusseldorf 2019. E. coli Colony PCR. **protocols.io** <https://dx.doi.org/10.17504/protocols.io.76ihrce>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
 We use this protocol and it's working

Created: Oct 14, 2019

Last Modified: Oct 14, 2019

PROTOCOL integer ID:
 28586

- Transfer cells from a single colony (8 in total) using a sterile P2 pipette tip.
- Run thermocycler using the following program (extension for 1.5 kb insert):

	Step	Temp (°C)	Time (mm:ss)	Purpose
	1	95	3:00	Initial Denaturation
	25 cycles of Steps 2 to 4:			
	2	95	0:20	Denaturation
	3	57	0:30	Annealing
	4	72	1:00	Extension
	5	72	5:00	Final Extension
	6	4	∞	Storage

- Analyze bands on a 1% Agarose gel:

(no amplification if Gene is missing or in wrong direction when using gene specific primer)

(Smaller than expected band if no insert is present when using two vector specific primer)