VERSION 3

OCT 17, 2019

OPEN ACCESS

DOI:

dx.doi.org/10.17504/protocols.io.8d2hs8e

Protocol Citation: Bulent Arman Aksoy, Pinar Aksoy, Elinor Gottschalk, Jeff Hammerbacher 2019. Flow-cytometry-based in vitro assay for assessing T-cell-mediated cytotoxicity against a target cell line (24-well plate, pmel-1 or OT-I T cells, MC38 cell line). **protocols.io** <https://dx.doi.org/10.17504/protocols.io.8d2hs8e>

MANUSCRIPT CITATION:

Viable and efficient electroporation-based genetic manipulation of unstimulated human T cells Pinar Aksoy, Bülent Arman Aksoy, Eric Czech, Jeff Hammerbacher bioRxiv 466243; doi: <https://doi.org/10.1101/466243>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](https://creativecommons.org/licenses/by/4.0/), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Flow-cytometry-based in vitro assay for assessing T-cell-mediated cytotoxicity against a target cell line (24-well plate, pmel-1 or OT-I T cells, MC38 cell line) V.3

Bulent Arman Aksoy¹, Pinar Aksoy¹, Elinor Gottschalk¹, Jeff Hammerbacher¹

¹Medical University of South Carolina

Hammer Lab

Tech. support phone: +18437924527 email: arman@hammerlab.org

Bulent Arman Aksoy

Medical University of South Carolina

ABSTRACT

In vitro co-cultures of cytotoxic T cells with their target cells are important assays to assess the functionality of the T cells in a scalable way. These assays rely on co-culturing CD8 T-cells, often times genetically modified to express a specific TCR or CAR, with another type of cell line that can be recognized by T cells. Co-cultures are typically run for 6-24 hours and then the amount of cells that were killed in the co-culture can be assessed through different techniques – e.g. radioactive Cr or non-radioactive LDH release assays. Here, we outline another alternative to these release assays which relies on flow cytometry to estimate the number of target cells left in the culture after a certain period of time.

MATERIALS

MATERIALS

Trypsin 0.05% 1X Solution **VWR International Catalog #16777-202**

CytoOne 24-well TC plate **USA Scientific Catalog #CC7682-7524**

APC anti-mouse CD3 Antibody **BioLegend Catalog #100235**

PerCP anti-mouse CD8a Antibody **BioLegend Catalog #100731**

pmel-1 mouse (B6.Cg-Thy1a/Cy Tg(TcraTcrb)8Rest/J) **Jackson Laboratory Catalog #005023**

OT-I mouse (C57BL/6-Tg(TcraTcrb)1100Mjb/J) **Jackson Laboratory Catalog #003831**

STEP MATERIALS

Trypsin 0.05% 1X Solution **VWR International Catalog #16777-202**

PerCP anti-mouse CD8a Antibody **BioLegend Catalog #100731**

APC anti-mouse CD3 Antibody **BioLegend Catalog #100235**

Protocol status: Working
We use this protocol and it's working

Created: Oct 17, 2019

Last Modified: Oct 17, 2019

PROTOCOL integer ID:
28826

Keywords: T cells,
cytotoxicity, co-culture, MC38,
TCR, CAR, flow cytometry,
CD3, CD8

BEFORE START INSTRUCTIONS

- Make sure you have enough activated (for at least 3 days), healthy (>50% viability), and cytotoxic (CD8) T cells in culture before starting
- Make sure you have access to a flow-cytometer after the co-culture is done
- When in doubt, use 24-well plates for the co-culture
- Make sure the cell line expresses the target protein (for CAR) or presents the relevant peptide (for TCRs) up-front
- Make sure the cell line can grow and sustain viability in T cell media throughout the co-culture
- Make sure the final T cell concentration doesn't go higher than 2 million per mL since this can cause stress on the T cells and the cell line
- This protocol assumes the assay is carried out at 8:1 T-cell:Cell-line ratio. Please scale the numbers up if you would like to assay at a different scale/ratio
- When in doubt, use OT-I CD8 T cells against MC38s that are pulsed with the SIINFEKL peptide as a positive control
- When in doubt, use OT-I CD8 T cells against MC38s that are NOT pulsed with the SIINFEKL peptide as a negative control
- This protocol assumes the T cells and the cancer cells are of mouse origin. If you are using a different organism or the channels are not appropriate for your flow-cytometer, please customize your antibodies accordingly

Day 0 - Seeding the target cells

- 1 Collect at least 3 million MC38s by trypsinizing them from an on-going culture
- 2 Spin them down at 200 x g for 00:05:00 at 4 °C and re-suspend them in fresh media at a 250,000 cells per mL concentration
- 3 Seed each 24-well-plate well with 500 uL of the cell suspension (i.e. 125,000 MC38 cells per plate)
- 4 Incubate overnight and allow cells to adhere to the plate

Day 1 - Co-culture

- 5 Collect 2 million cytotoxic T cells per sample (i.e. per well) from an on-going culture
- 6 Spin them down at 350 x g for 00:05:00 at 4 °C and re-suspend them in fresh media at 1 million per mL concentration
- 7 Supplement T cells with 200 IU/mL rIL2
- 8 Aspirate the culture media from each of the 24-well-plate wells that contain a sample. Try to aspirate as much as possible but make sure you don't disturb the adherent cells during this process
- 9 Add 2 mL of the T cell suspension onto each of the sample wells. Assuming that the cancer cell line doubled overnight, this would result in a 8:1 (2 million:250K) T-cell:MC38 ratio.
- 10 For positive controls (samples that are expected to get killed), if the cancer cell line doesn't express or present the target protein/epitope, make sure to supplement the co-culture with the target peptide.

Note

- For pmel-1 CD8 cells, the co-culture should be supplemented with the hgp100 at 0.96 ug/mL (i.e. 1 micromolar (μ M)) at the beginning of the culture
- For OT-I CD8 cells, the co-culture should be supplemented with the SIINFEKL at 9.63 ug/mL (i.e. 10 micromolar (μ M)) at the beginning of the culture

- 11 Incubate the co-culture for at least 16 hours (overnight) before assaying.

Day 2 - Flow-cytometry-based cytotoxicity assesment

- 12 Prepare and label 2 mL eppendorf tubes for each of your samples
- 13 Using a P1000, thoroughly pipette up and down each well and transfer everything in the well over to the corresponding 2 mL tube
- 14 Without letting the well to dry out too much (> 2 minutes), add 200 μ L of trypsin and incubate at Room temperature for 00:02:00 .
- Trypsin 0.05% 1X Solution **VWR International Catalog #16777-202**
- 15 Stop the trypsinization by adding 800 μ L of culture media into each well
- 16 Spin down the tubes at 350 x g for 00:05:00 and aspirate 1 mL from the top without disturbing the cell pellet. Then transfer the 1 mL of trypsinized cells over to the corresponding tube. Spin down the tubes at 350 x g for 00:05:00 and aspirate the supernatant.
- 17 Re-suspend the cell pellet in 1 mL flow buffer and add 5 μ L from each of the antibodies.

PerCP anti-mouse CD8a Antibody **BioLegend Catalog #100731**

Note

Make sure to pick two markers that will distinguish one cell from the other. We have found CD3 and CD8 staining, together, can help easily distinguish T cells from the cancer cells. Given that it is not easy to gate cells out only using the FSC/SSC channels, having these extra stains increase the specificity.

18 Stain the cells for 00:20:00 at Room temperature or 00:30:00 at 4 °C

19 Spin the cells down at 350 x g for 00:05:00, remove the supernatant, and re-suspend them in 400 µL PBS.

20 Run 200 µL of the sample fully on flow (i.e. do not limit the number of events).

Note

Since the cancer cells co-cultured with lots of T cells can easily clog the flow cytometer, having half of the sample as a back-up always helps.

Analysis

21 To count the number of MC38s left in the dish,

- Using your MC38 samples that were cultured on their own first, define the viable population as your initial gate (G0)
- Within your G0, open the CD3/CD8 stain channels and gate the double-negative population (MC38s)

22 Normalize the positive samples against their corresponding negative controls to estimate the fraction of MC38 that are left in the plate. Subtracting this from 100% would give you an

estimate of how much cytotoxicity happened for that particular sample.

Expected result

At 8:1 OTI:MC38 ratio, 16 hours co-culture should yield >70% cytotoxicity when the number of MC38s left in the SIINFEKL-pulsed well is normalized against the unpulsed well.