APR 15, 2020

Sample preparation to mass spectrometer using ZipTip_{C18}

Neilier
Junior¹

¹Universidade Federal de Viçosa

Neilier Junior

Universidade Federal de Viçosa, University of Manitoba

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.be45jgy6

Protocol Citation: Neilier Junior 2020. Sample preparation to mass spectrometer using ZipTipC18. **protocols.io** <https://dx.doi.org/10.17504/protocols.io.be45jgy6>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
We use this protocol and it's working

Created: Apr 15, 2020

Last Modified: Apr 15, 2020

PROTOCOL integer ID:
35709

ABSTRACT

ZipTip is a 10 µL pipette tip that aims to concentrate and purify from femtomols to picomols protein and oligopeptide .

MATERIALS

MATERIALS

- ✕ ZipTipC18 Merck Millipore
- ✕ MilliQ Water Contributed by users
- ✕ Acetonitrile Sigma Aldrich Catalog #34998
- ✕ Pierce™ Trifluoroacetic Acid (TFA), Sequencing grade Thermo Fisher Catalog #28904

- Kimwipes
- P-10 pipettor
- 1.5 mL microtubes
- 0,2 mL microtubes

SAFETY WARNINGS

- ! The contamination of the samples during the preparation is somewhat recurrent and this can compromise the analysis by LC-MS / MS. To avoid contaminants such as saliva and keratin, wear personal protective equipment: mask, gloves and lab coat

BEFORE START INSTRUCTIONS

Make sure all reagents and equipment are available. Plan the experiment!

Prepare the materials and workspace

- 1 Calibrate the P-10 pipette to 10 μ L.
- 2 Name 4 microtubes of 1.5 mL with the respective reagents:
 - ACN_{100%} (I)
 - TFA_{0.1%} (I)
 - TFA _{0.1%} (II)
 - ACN_{100%} (II)

Add 1 mL of the respective solutions to the tubes above.
- 3 Name new 0.2 mL microtubes with sample names followed by "zt".
- 4 Aliquot 50 μ L of ACN 100% in each "zt" tube.
- 5 Fit the ZipTip with the pipette already attached, so as not to pass air through the "chromatographic column". Hold down until you start the procedure with the first pipetting.

Procedure

- 6 ■ **Cleaning and preparation:** ACN_{100%} (I)

Pipette the acetonitrile from the ACN_{100%} (I) tube 10 times, discarding the contents on the kimwipes

7 ■ **Equilibrate:** TFA_{0.1%} (I)

Pipette the acetonitrile from the TFA_{0.1%} (I) tube 10 times, discarding the contents on the kimwipes

8 ■ **Binding of peptides (analyte):** sample tube

Homogenize the sample with ZipTip 20 times

9 ■ **Wash:** TFA_{0.1%} (II)

Pipette the acetonitrile from the TFA_{0.1%} (II) tube 10 times, discarding the contents on the kimwipes

10 ■ **Elution:** ACN_{100%} (II)

Homogenize 20 times in the “zt” tube, already with 50 µL of ACN_{100%}

11 ■ **Shutdown:** ACN_{100%} (II)

Pipette the acetonitrile from the ACN_{100%} (II) 10 times, discarding in the “zt” tube.

NOTE

- 12** During the entire process, no air should enter through ZipTip. Pipetting should be done slowly to maximize chemical interactions