VERSION 1

APR 29, 2020

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.bfijjkce

Protocol Citation: Payal Patel, Bethany Rozeboom, Tarah-Anne Abrigo 2020. Western Blot . [protocols.io](https://dx.doi.org/10.17504/protocols.io.bfijjkce)
<https://dx.doi.org/10.17504/protocols.io.bfijjkce>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
 We use this protocol and it's working

Created: Apr 24, 2020

Last Modified: Apr 29, 2020

PROTOCOL integer ID:
 36138

Western Blot V.1

Payal Patel¹, Bethany Rozeboom¹, Tarah-Anne Abrigo¹

¹Mercer University, Biochemistry Senior Capstone

Bethany Rozeboom

MATERIALS

MATERIALS

- ⊗ 2x Laemmli Sample Buffer **BioRad Sciences Catalog #1610737**
- ⊗ TE buffer **Thermo Fisher Scientific**
- ⊗ Bio Rad Precision Plus protein Standard **Bio-rad Laboratories Catalog #161-0374**
- ⊗ Tryptic Soy Broth, E - 10mL **Thermo Fisher Catalog #R07226**
- ⊗ SignalFire™ ECL Reagent **Cell Signaling Technology Catalog ##6883S**
- ⊗ Tris Buffered Saline (TBS-10X) **Cell Signaling Technology Catalog ##12498**
- ⊗ Tris-Glycine Transfer Buffer (10X) **Cell Signaling Technology Catalog ##12539**
- ⊗ Tris-Glycine SDS Running Buffer (10X) **Cell Signaling Technology Catalog ##4050**
- ⊗ Tris Buffered Saline with Tween® 20 (TBST-10X) **Cell Signaling Technology Catalog ##9997**
- ⊗ Nonfat Dry Milk **Cell Signaling Technology Catalog ##9999**
- ⊗ BSA **Cell Signaling Technology Catalog ##9998**
- ⊗ Anti-mouse IgG HRP-linked Antibody **Cell Signaling Technology Catalog ##7076**

Cell Preparation

- 1 Grow cell 50 mL of TSB, let incubate Overnight
- 2 Distributed 17 mL of culture into two 50 mL centrifuge tubes, and 10 mL into one 20 mL centrifuge tube
- 3 Centrifuge down for 00:20:00 at 4300rpm (4303 xg) 4 °C
- 4 Aspirate media from cultures; wash cells 3x with TE aspirate.
- 5 Lyse cells by resuspending in 1 mL of the different lysis buffers
 - 5.1 20 millimolar (mM) Tris Cl , 15 millimolar (mM) NaCl , 0.9696% Triton 7.5 (labelled A)
Phosphatase Inhibitor: 50 millimolar (mM) NaF ,
1 millimolar (mM) Sodium Orthovanadate ,
10 millimolar (mM) Sodium Pyrophosphate and
10 millimolar (mM) B-glycerophosphate
EDTA-free Protease tablet (1 tablet per 10 mL)
 - 5.2 1% SDS, 10 mL Tris Cl , 1 millimolar (mM) EDTA (labelled B)
Phosphatase Inhibitor: 50 millimolar (mM) NaF ,
1 millimolar (mM) Sodium Orthovanadate ,
10 millimolar (mM) Sodium Pyrophosphate and
10 millimolar (mM) B-glycerophosphate

EDTA-free Protease tablet (1 tablet per 10 mL)

- 6 Freeze thaw 3 times
- 7 Sonicated for 00:01:00 , repeat 5 times
- 8 Centrifuged at 13000 rpm for 00:05:00
- 9 Bradford Assay
- 10 Combine 40 μ L 4X Laemmli to cell lysate, 40 μ L of Lysis A and Lysis B
- 11 Load 40 μ L onto SDS-PAGE gel and 40 μ L of All Blue Precision Plus for ladder
- 12 Soaked sponges and transfer paper in Transfer Buffer
- 13 Soak PVDF membrane in Methanol

- 14** Soak fiber pads thoroughly in a Transfer Buffer
- 15** Make the blotting sandwich
- 15.1** Add 1 cm depth of Transfer Buffer to container and insert plastic cassette with black side down, lay a wet fiber pad on the black side of the cassette
- 15.2** Lay one wet blotting paper on the fiber pad and roll out air bubbles
- 15.3** Lay gel squarely on blotting paper and roll out air bubbles
- 15.4** Lay wet PVDF on the gel and roll out air bubbles
- 15.5** Lay one wet blotting paper on the membrane and roll out air bubbles
- 15.6** Lay a wet fiber pad on top of the blotting paper and close the cassette and clamp together with the white clip.
- 16** Electrotransfer to PVDF membrane at 30 mV Overnight

Membrane Blocking

- 17 After transfer, wash PVDF membrane with 25 mL TBS for 00:05:00 at Room temperature
- 18 Incubate membrane in 25 mL Blocking Buffer for 01:00:00 at Room temperature
- 18.1 Combine 7.5 g Nonfat dry Milk with 150 mL TBST to make Blocking Buffer
- 19 Wash three times for 00:05:00 each with 15 mL TBST
- 20 Incubate membrane in Primary Antibody (at 1:2000) in a 10 mL Primary Antibody Dilution Buffer with gentle agitation Overnight
- 20.1 Combine 1.0 g 5% BSA to 20 mL 1X TBST and mix well
- 21 Wash three times for 00:05:00 each with 15 mL TBST
- 22 Incubate membrane with Anti-mouse IgG, HRP-linked Antibody (1:1000) to detect biotinylated

protein markers in 10 mL Blocking Buffer with gentle agitation for 01:00:00 at Room temperature

23 Wash three times for 00:05:00 each with 15 mL TBST

Detection of Proteins

24 Prepare 1X SignalFire™ ECL Reagent (#6883) by diluting one part 2X Reagent A and one part 2X Reagent B (based off of the size of our membrane we mixed 1 mL of each together)

25 Incubate substrate with membrane for 00:07:00, remove excess solution (membrane remains wet) expose to X-ray film using an imager