



Sep 10, 2024

🌐 Indirect Co-Culture Assay using Boyden Chambers

📖 Journal of Extracellular Biology

DOI

<https://dx.doi.org/10.17504/protocols.io.5jyl82om7l2w/v1>


Bianca Cruz Pachane¹, Heloisa Sobreiro Selistre de Araujo¹

¹Universidade Federal de São Carlos - UFSCar



Bianca Cruz Pachane

Universidade Federal de São Carlos - UFSCar



Create & collaborate more with a free account

Edit and publish protocols, collaborate in communities, share insights through comments, and track progress with run records.

Create free account

OPEN  ACCESS



DOI: <https://dx.doi.org/10.17504/protocols.io.5jyl82om7l2w/v1>

External link: <https://doi.org/10.1002/jex2.70075>

Protocol Citation: Bianca Cruz Pachane, Heloisa Sobreiro Selistre de Araujo 2024. Indirect Co-Culture Assay using Boyden Chambers. **protocols.io** <https://dx.doi.org/10.17504/protocols.io.5jyl82om7l2w/v1>

**Manuscript citation:**

Pachane BC, Bottaro PHT, Machado AM, Castro CAd, Guerra G, Gozzer LT, Grigoli MM, Zutião AD, Fuzer AM, Cominetti MR, Altei WF, Selistre-de-Araujo HS (2025) Tumoural Hypoxic Extracellular Vesicles Foster a Protective Microenvironment in Triple-Negative Breast Cancer. Journal of Extracellular Biology 4(9). doi: [10.1002/jex2.70075](https://doi.org/10.1002/jex2.70075)

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working

We use this protocol and it's working

Created: September 09, 2024

Last Modified: September 10, 2024

Protocol Integer ID: 107204

Keywords: Boyden chamber, Zymography, Co-culture, Invasion assay, tumor microenvironment, tumor microenvironment without direct contact, transwell assay, tumoral invasion, tumoral evs in cell, culture assay, intercellular adhesion, using boyden chamber, cell line, tumoral ev, effect of hypoxic, assay, cell, hypoxic, boyden chamber, porous membrane

Funders Acknowledgements:

São Paulo Research Foundation

Grant ID: 2021/01983-4

Disclaimer

DISCLAIMER – FOR INFORMATIONAL PURPOSES ONLY; USE AT YOUR OWN RISK

The protocol content here is for informational purposes only and does not constitute legal, medical, clinical, or safety advice, or otherwise; content added to [protocols.io](#) is not peer reviewed and may not have undergone a formal approval of any kind. Information presented in this protocol should not substitute for independent professional judgment, advice, diagnosis, or treatment. Any action you take or refrain from taking using or relying upon the information presented here is strictly at your own risk. You agree that neither the Company nor any of the authors, contributors, administrators, or anyone else associated with [protocols.io](#), can be held responsible for your use of the information contained in or linked to this protocol or any of our Sites/Apps and Services.

Abstract

Here, we describe a transwell assay using Boyden chambers as an indirect co-culture method, where two cell lines are grown together but separated by a porous membrane. This assay was used to determine the effect of hypoxic, tumoral EVs in cells from the tumor microenvironment without direct contact between them, focusing on intercellular adhesion and tumoral invasion.

Image Attribution

Experimental diagram created using BioRender.com and Adobe Photoshop.

Materials

Materials and reagents

1. Sterile microtubes and pipettes
2. 24-well plates, Corning - Catalog #3337
3. Round glass coverslips 13mm $\varnothing$
4. Falcon® Permeable Support for 24-well Plate with 3.0 μ m Transparent PET Membrane, Corning - Catalog #353096
5. Falcon® Permeable Support for 24-well Plate with 8.0 μ m Transparent PET Membrane, Corning - Catalog #353097
6. Poly-L-Lysine (PLL 0.1 % (w/v) in H₂O), Sigma-Aldrich - Catalog #P8920
7. Glutaraldehyde, 50% in H₂O, Sigma-Aldrich - Catalog #G6403
8. Gelatin From Pig Skin, Fluorescein Conjugate, Thermo Fisher - Catalog #G13187
9. Sterile PBS
10. OptiMEM I Reduced Serum Media, Gibco - Catalog #31985070
11. Trypan Blue solution 0.4%, Merck Millipore (Sigma-Aldrich) - Catalog #T8154-100 ml
12. Paraformaldehyde solution (PFA 4% in deionized water, pH 7.6 - Sterile)
13. Triton X-100 0.1% (v/v) in deionized water
14. Phalloidin + DAPI (1 μ l Phalloidin-iFluor 647, Abcam - Catalog #ab176759 + 0.76 μ L 4,6-Diamidino-2-Phenylindole, Dihydrochloride (DAPI), Thermo Fisher Scientific - Catalog #D1306 in 5 mL PBS)
15. Scalpel
16. Fluoromount mounting media, Sigma-Aldrich - Catalog #F4680
17. Histological slides, Exacta.
18. Pierce™ BCA Protein Assay Kit, Thermo Fisher - Catalog #23227
19. Precision Plus Protein™ Dual Color, Bio-Rad - Catalog #1610374

Cell lines and growth media

- MDA-MB-231 (ATCC® CRM-HTB-26™) - Leibovitz L-15 10% FBS
- HDFa (ATCC® PCS-201-012™) - DMEM 10% FBS 1% pen/strep
- HUVEC (ATCC® CRL-1730™) - DMEM 10% FBS 1% pen/strep

Equipments:

1. Biological cabinet
2. Cell incubator (37 °C, 5% CO₂)
3. Cell counter - TC20 Cell Counter, Bio-Rad - Catalog #1450011
4. Epifluorescence microscope - ImageXpress Micro XLS, Molecular Devices - Catalog #500496
5. Orbital shaker
6. Mini-PROTEAN Tetra Vertical Electrophoresis System, Bio-Rad - Catalog #1658033FC
7. ChemiDOC XRS+ Gel Imaging System, Bio-Rad - Catalog #1708265EDU



Protocol materials



Parafilm[®]; M Laboratory Wrapping Film, 4 in. W x 125 ft. L; (10cm x 38m) **Thermo**
Fisher Catalog #1337410

Safety warnings



Light-sensitive assay. Work under sterile conditions.

Before start

Fluorescent gelatin preparation: Under sterile conditions, solubilize the fluorescent gelatin stock at **37 °C** with warmed PBS following the manufacturer's instructions for a concentration of **5 mg/mL**. Aliquot in microtubes and maintain at -20 °C until time of use.

Before use, thaw gelatin at **37 °C** for **00:30:00**. Dilute stock to a **0.2 mg/mL** working solution with warmed PBS and maintain at **37 °C** until use.

Cell culture: Maintain cells in culture during at least two passages after thawing.



Preparation of Gelatin-Coated Coverslips

20m

1 In preparation:

1. Clean *round glass coverslips* (13 mm $\varnothing$) with 70% ethanol wipes before use. Maintain slips in a clean container.
2. Prepare a 0.5 % (v/v) glutaraldehyde solution in H₂O and keep at 4 °C until use, protected from light.

- 2 Under sterile conditions, apply 20 μ L of PLL solution (0.1 mg/ml) in spaced droplets to a surface covered in

 Parafilm[®]; M Laboratory Wrapping Film, 4 in. W x 125 ft. L; (10cm x 38m) **Thermo Fisher Catalog #1337410**

- 3 Drop coverslips atop the droplets and incubate at Room temperature for 00:20:00 minimum .

20m

- 4 Using forceps, transfer the coverslip to a 24-well plate with the coating facing upwards.

- 5 Wash coverslips twice with 500 μ L PBS.

- 6 Cross-link coating with 500 μ L of cold 0.5 % (v/v) glutaraldehyde for 00:15:00 at Room temperature

15m



- 7 Prepare a Petri dish with the bottom covered in

 Parafilm[®]; M Laboratory Wrapping Film, 4 in. W x 125 ft. L; (10cm x 38m) **Thermo Fisher Catalog #1337410**

- 8 Apply spaced 20 μ L droplets of the fluorescent gelatin working solution at 0.2 mg/mL to the Parafilm-covered surface.

- 9 Remove the coverslips from the 24-well plate and drop them atop the droplets, with the coating facing down. Incubate at 4 °C Overnight , protected from light.

20m





10 The next day, remove the slips from the Petri dish using a forceps and transfer them, with the coating facing up, to a fresh 24-well plate.

11 Wash coverslips thrice with  500 μ L PBS.

11.1 *Slips can be stored at 4 °C for up to a week, wrapped in aluminium foil.*



12 Pre-condition gelatin coating with  500 μ L of Leibovitz L-15 10% FBS for

30m

 00:30:00 at  37 °C without CO₂.



MDA-MB-231 Seeding in Gelatin-Covered Coverslips

13 Subculture cells as usual. Resuspend cell pellets in Leibovitz L-15 10% FBS and count cells using the trypan blue exclusion method.

14 Remove the pre-conditioning medium from the 24-well plate.

15 Seed 5×10^4 cells in  1000 μ L Leibovitz L-15 10% FBS in each well. Seal the plate with

 Parafilm[®]; M Laboratory Wrapping Film, 4 in. W x 125 ft. L; (10cm x 38m) **Thermo Fisher Catalog #1337410**

16 Incubate cells at  37 °C without CO₂  Overnight for adhesion.



HUVEC Seeding in Transwell Insert

17 Subculture cells as usual. Resuspend cell pellets in DMEM 10% FBS 1% pen/strep and count cells using the trypan blue exclusion method.

18 Add  750 μ L DMEM 10% FBS 1% pen-strep to the wells of a 24-well plate (Corning).

19 Assemble a Boyden chamber using a 24-well plate and 3.0 μ m inserts (Falcon).



20 Seed 5×10^4 cells in  250 μ L DMEM 10% FBS 1% pen/strep to the upper chamber.

21 Incubate cells at  37 °C 5% CO₂  Overnight for adhesion.



HDFa Seeding in Transwell Insert

22 Subculture cells as usual. Resuspend cell pellets in DMEM 10% FBS 1% pen/strep and count cells using the trypan blue exclusion method.

23 Add  750 μ L DMEM 10% FBS 1% pen-strep to the wells of a 24-well plate (Corning).

24 Assemble a Boyden chamber using a 24-well plate and 8.0 μ m inserts (Falcon).

25 Seed 2×10^3 cells in  250 μ L DMEM 10% FBS 1% pen/strep to the upper chamber.

26 Incubate cells at  37 °C 5% CO₂  Overnight for adhesion.



Indirect Co-Culture Assembly

1d

27 Remove the growth media from all wells and Boyden chambers (both the upper and the lower chambers).

28 Transfer the MDA-MB-231 coverslips to a fresh well.

29 Add  750 μ L OptiMEM to the coverslip-containing wells.

30 Transfer either the HUVEC or the HDFa inserts to the wells.

31 Add  250 μ L OptiMEM containing EVh (10^9 particles/ml) or the equivalent treatment volume in PBS to the upper chamber.



32 Incubate cells at 37 °C 5% CO₂ for 24:00:00

1d



Fixation and Cell Staining

10m

33 Collect both the upper and the lower chamber's supernatant into a 1.5 ml microtube. Keep On ice . This will be processed later for gelatin zymography -

[go to step #67](#)

34 Transfer the inserts to new wells.

35 Fix cells with 1000 µL 4% PFA for 00:10:00 at Room temperature

10m



36 Wash wells twice with 500 µL PBS.

37 Clean the outside part of the insert membrane with a swab to remove any debris.



38 Permeabilize cells with 100 µL 0.1% Triton X-100 at Room temperature for 00:05:00

5m



39 Wash wells twice with 500 µL PBS.

40 Stain cells with the DAPI + Phalloidin-647 mixture. Add 20 µL of staining solution in spaced droplets to a Parafilm-covered surface. Drop coverslips (coating facing down) and insert membranes atop the droplets and incubate at Room temperature , protected from light for 00:20:00

20m



41 Wash wells twice with 500 µL PBS.



- 42 Assemble coverslips to clean histological slides using Fluoromount as mounting media. Allow slide to dry for at least  04:00:00 , protected from light. 4h
- 43 Detach membranes from inserts using a scalpel. Assemble the membranes in histological slides using Fluoromount as mounting media. Seal the membrane with a rectangular coverslip and allow slide to dry for at least  04:00:00 , protected from light. 4h
- 44 Once dry, seal coverslips using clear nail polish and store at  4 °C until time of analysis.

Cell Imaging by Epifluorescence HTS

- 45 Using the microscope ImageXpress Micro XLS+ (Molecular Devices), check the template for the histological slides and the filters for DAPI (nuclei), FITC (gelatin - for MDA-MB-231 only) and Cy5 (phalloidin-647). 
- 46 Set laser intensity to a minimum of 10 ms and increase gradatively if necessary. 
- 47 Check the wells using the 4X objective. 
- 48 Change into the 20x objective and adjust the laser focus. Select 9 sites per well minimally. 
- 49 Acquire the plate. Export metadata for analysis. 
- 50 For representative images, change to the 40x objective and adjust the laser focus. Select the sites of interest and acquire. Export image channels and combinations. 

Gelatin Degradation Quantification on FIJI

- 51 On FIJI (ImageJ), import HTD files through BioFormats. 
- 52 Images should already be scaled. If not, adjust scale based on the objective lens used for acquisition. 



- 53 Set measurements to contain "Area", "Standard Deviation", "Shape Descriptor", "Mean grey value", "Perimeter" and "Display label".
- 54 Concatenate all stacks into a single hyperstack.
- 55 Split channels and select the FITC stack for analysis.
- 56 Set a threshold to encompass the degradation spots but not the background. Write down the threshold values. Create a new stack with the binary images.
- 57 To measure the degraded area, analyze particles with a range of "5-Infinity" and select "Summarize".
- 58 Save CSV file. The degraded area (in μm^2) per site will be compared between groups in the statistical analysis.

Cell Morphology Analysis on FIJI

- 59  [go to step #51](#) and follow until step #54
- 60 Split channels and select the Cy5 stack for analysis.
- 61 Duplicate Cy5 stack.
- 62 Set a threshold to encompass cell cytoplasm. Create a new stack with the binary images.
- 63 Using the duplicated stack as a guide, section cells using the "pencil" tool with a 3 px thickness.
- 64 To analyze cell morphology, analyze particles with a range of "10-Infinity" and check "Clear Results".



- 65 Save CSV file. The cell circularity index of each cell will be compared between groups in the statistical analysis.



Gelatin Zymography of Assay Supernatant

10m

- 66 Prepare 10% SDS-PAGE gels containing gelatin (100 mg/ml) using the Mini-PROTEAN system (Bio-Rad) with 0.75 mm spacers. Maintain gels hydrated at 4 °C



Overnight after polymerization.

- 67 Spin the assay conditioned media at 1200 rpm, 4°C, 00:10:00 . Transfer the supernatant to new tubes and discard pellet.

10m



- 67.1 Store microtubes at -80 °C until the time of analysis.
Thaw microtubes On ice before the next step and avoid freeze/thawing cycles.



- 68 Quantify the supernatants using the Pierce™ BCA Protein Assay kit, following the manufacturer's instructions. A plate reader is required for this step.

- 69 Aliquot samples in microtubes to contain 15 µg of protein per well.

- 70 Mix samples with non-reducing Laemmli sample buffer (10 % (w/v) SDS ; glycerol; 0.1 Molarity (M) EDTA ; 1 Molarity (M) Tris-HCl pH 6.8 ; bromophenol blue) at a 1:2 ratio.

- 71 Assemble gels in running buffer and load samples onto gels alongside a protein ladder (Precision Plus Protein™ Dual Color, Bio-Rad).

- 72 Run electrophoresis at 80 V at 4 °C for circa 04:00:00 .

4h



- 73 Transfer gels onto cases and photograph them using the ChemiDOC Imaging System (Bio-Rad).





- 74 Wash gels with [M] 2.5 % (v/v) Triton X-100 for ⌚ 00:40:00 under orbital agitation. 40m 
- 75 Incubate gels in buffer ([M] 50 millimolar (mM) Tris, [M] 5 millimolar (mM) CaCl₂ pH 8.0, [M] 0.02 % (w/v) sodium azide, [M] 10 millimolar (mM) ZnCl₂) at 🌡 37 °C for ⌚ 20:00:00 20h  
- 76 Stain gels with Coomassie Brilliant Blue for ⌚ 24:00:00 under agitation at 🌡 Room temperature . 1d 
- 77 Destain gels with acetic acid:methanol:water (1:1:8, v/v) for up to ⌚ 48:00:00 2d 
- 78 Photograph gels using the ChemiDOC Imaging System (Bio-Rad). 
- 79 Perform a band densitometry analysis in each gel. 

Protocol references

BOYDEN, Stephen. THE CHEMOTACTIC EFFECT OF MIXTURES OF ANTIBODY AND ANTIGEN ON POLYMORPHONUCLEAR LEUCOCYTES. **The Journal of Experimental Medicine**, [s. l.], v. 115, n. 3, p. 453–466, 1962.

LEBER, Thomas M.; BALKWILL, Frances R. Zymography: A Single-Step Staining Method for Quantitation of Proteolytic Activity on Substrate Gels. **Analytical Biochemistry**, [s. l.], v. 249, n. 1, p. 24–28, 1997.

PACHANE, Bianca Cruz et al. Small Extracellular Vesicles from Hypoxic Triple-Negative Breast Cancer Cells Induce Oxygen-Dependent Cell Invasion. **International Journal of Molecular Sciences**, [s. l.], v. 23, n. 20, p. 12646, 2022.

EVEN-RAM, Sharona; ARTYM, Vira. **Extracellular Matrix Protocols: Second Edition**. [S. l.]: Humana Press, 2009.