OCT 28, 2020

🌐 Ampure bead clean up for high molecular weight DNA

📁 In 1 collection

Natalie Solonenko¹

¹The Ohio State University

Sullivan Lab

Marie Burris

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.6kphcvn

Protocol Citation: Natalie Solonenko 2020. Ampure bead clean up for high molecular weight DNA . **protocols.io**
<https://dx.doi.org/10.17504/protocols.io.6kphcvn>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
We use this protocol and it's working

Created: Aug 16, 2019

Last Modified: Oct 28, 2020

PROTOCOL integer ID:
26991

GUIDELINES

For sample, do not vortex or mix by pipetting throughout protocol. This is to avoid shearing DNA.

MATERIALS

MATERIALS

Agencourt AMPure XP beads **Contributed by users**

BEFORE START INSTRUCTIONS

Turn on a heat block to 55 °C

Add beads

- 1 Make sure beads are completely resuspended before use by vortexing vigorously.

- 1.1 Add ratio of resuspended beads specified in your main protocol.

Note

This ratio is dependent on the length of DNA you want to recover.

- 1.2 Flick tube gently to mix beads and sample.

Incubate

- 2 Incubate at room temperature for 5 minutes.

Room temperature

00:05:00

Note

Flick gently periodically throughout the incubation to prevent beads from settling to the bottom of the tube.

Separation

- 3 Place tubes on a magnetic rack.
■ see below for example.

Equipment

Magnetic Stand

NAME

Magnetic Stand

TYPE

Thermo Scientific

BRAND

MR02

SKU

<https://www.thermofisher.com/order/catalog/product/MR02>

LINK

Any magnetic rack that fits your tubes will suffice.

SPECIFICATIONS

- 3.1 Wait 2 min for the beads and buffer to seaparate. Beads will stick to magnetic side of the tube and the solution should be clear.
- 3.2 Remove and discard the clear solution. DNA will remain in the tube bound to the beads.

Wash

- 4 Add 500ul 80% EtOH to each sample.
 - Do not disturb the beads! Pipette into the opposite side of the tube.

Note

Volume of 80% EtOH can be adjusted. Just so long as the amount added is enough to cover beads.

- 4.1 Incubate at room temperature for 30 seconds.

🌡 Room temperature

🕒 00:00:30

4.2 Remove 80% EtOH, being careful not to disturb the beads.

5 Repeat the step 4.

6 Spin down briefly and place back on the magnetic stand. Remove residual EtOH.

Dry Beads and Resuspend DNA

7 Leaving the caps open, remove tubes from magnet, and dry until surface of the beads has a matte finish.

Note

Caution: If the surface of beads appear cracked, they are overdrying! Resuspend *immediately*. Over-dried beads will not resuspend well.

8 Resuspend DNA by adding a minimum of 15ul water or low EDTA TE and gently mix by flicking. The exact resuspension volume should be specified in your main protocol.

8.1 Incubate for 2 minutes at 55 C.

🌡 55 °C

🕒 00:02:00

Collect

9 Place tubes back on magnetic rack

9.1 Wait 2 min for the beads to seaparate. Beads will stick to magnetic side of the tube and the solution should be clear.

9.2 Pipette out your specified volume of eluate and keep as your sample.

Note

Do not carry over any beads! They are a significant inhibitor of various downstream aplications. Carefully check to your pipette tip for bead carryover. If there are beads, replace the sample into the tube and wait another 2 min. You may need to decrease the volume removed from the tube by 1-2 ul.