JUL 17, 2020

Ancient Proteins Extraction Protocol

In 1 collection

Ashley Scott¹, Christina Warinner¹

¹Max Planck Institute for the Science of Human History

WarinnerGroup

MPI EVA Archaeogenetics

Ashley Scott

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.7vwhn7e

Protocol Citation: Ashley Scott, Christina Warinner 2020. Ancient Proteins Extraction Protocol.
protocols.io
<https://dx.doi.org/10.17504/protocols.io.7vwhn7e>

MANUSCRIPT CITATION:
 Wisniewski, J.R., Zougman, A., Nagaraj, N., & Mann, M. (2009). Universal sample preparation method for proteome analysis. *Nature Methods*, 6, 359-362.

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
 We use this protocol in our group and it is working.

Created: Oct 02, 2019

Last Modified: Jul 17, 2020

ABSTRACT

This is a protocol for extracting total proteins from archaeological dental calculus. It is based on the filter-aided sample preparation (FASP) protocol first published by Wisniewski et al. 2009. Specific modifications have been made to enable protein extraction from calcified material and to ensure recovery of ancient proteins.

Working in an Ancient Protein Laboratory

- All steps of the protocol should take place in a dedicated clean room facility specifically designed for ancient proteins; do not extract or digest ancient proteins in a core facility laboratory where modern proteins are handled.
- Avoid introducing proteinaceous materials (e.g., latex, leather, silk, wool) into the lab. It is recommended that all laboratory clothing be made of cotton and shoes of synthetic materials.
- The researcher performing lab work should wear correspondingly suitable lab-wear, such as:
 - full-body suit with hood (e.g., Tyvek)
 - hairnet
 - face mask
 - two pairs of clean nitrile gloves
 - clean shoes
 - protective glasses
- Sample processing should be carried out in separated work benches (e.g. Dead Air PCR work bench)
- Surfaces and equipment should be regularly cleaned with water and/or ethanol or isopropanol and decontaminated with bleach solution.

Please see the following for more detailed guidance:

Hendy J, Welker F, Demarchi B, Speller C, Warinner C, Collins MJ. (2018) [A guide to ancient protein studies](#). *Nature Ecology and Evolution*. DOI: 10.1038/s41559-018-0510-x

MATERIALS

MATERIALS

☒ NaCl **Sigma Aldrich Catalog #53014**

☒ Sequencing Grade Modified Trypsin, 100ug **Promega Catalog #V5117**

☒ Trizma® hydrochloride solution **Sigma Aldrich Catalog #T2319**

☒ Trifluoroacetic acid for HPLC > 99.0% **Sigma-aldrich Catalog #302031-100ML**

☒ UltraPure 0.5M EDTA, pH 8.0 **Thermo Fisher Scientific Catalog #15575-038**

☒ Iodoacetamide **Sigma Aldrich Catalog #I1149-5G**

☒ Urea **Sigma Aldrich Catalog #U5378**

☒ DL-Dithiothreitol (DTT) **Sigma Aldrich Catalog #43815**

☒ Triethylammonium bicarbonate (TEAB) **Sigma Aldrich Catalog #T7408**

☒ SDS, 20% Solution, RNase-free **Thermo Fisher Catalog #AM9820**

Solutions:

1M DTT (if from powder). Add 15.43mg of DTT powder to 100uL of water

Lysis buffer:

-In a 1.5 mL Eppendorf tube, combine 90 µL 20% SDS stock solution, 45 µL 1M DTT stock solution, 45 µL 1M Trizma (Tris/HCl) with 270 µL milliQ water.

Urea (8M):

-In a 15 mL Falcon tube, add 10 mL Tris/HCl (100 mM) to 5.76 g urea powder. Bring the final volume up to 12 mL with Tris/HCl.

IAA: (0.05M)

-In a black 1.5 mL Eppendorf tube, add 1.5 mL urea solution (8M) to 13.87 mg of IAA powder

NaCl (0.5M):

-Add 2.922 g of NaCl to 100 mL of MilliQ water

TEAB (0.05M)

-Add 5mL of 1M TEAB to 95mL of MilliQ water

Trypsin solution (only do immediately prior to digestion step)

-Make trypsin solution. Add 1.2 mL TEAB (0.05 M) to 20 µg of lyophilized trypsin and resuspend thoroughly.

Sample Prep

1 Weigh samples (aim for 5-10 mg per sample) and place within a 1.5 mL Safelock Eppendorf tube.

1.1 Also prepare empty tubes for blank extractions that should be processed alongside your samples to monitor for lab contamination

Demineralization

2 Add 500 µL of 0.5 M EDTA to each sample, including extraction blanks.

3 Close tubes tightly and set on a rotator until calculus becomes completely dissolved (invisible), or buoyant and feathery, typically between 2-5 days.

EXTRACTION DAY 1

4 Prepare solutions and label all tubes that will be needed for Day 1

5 Spin down decalcified samples at 14,000 rcf for 5 minutes

6 Remove 300uL of EDTA supernatant and place in a new labeled sample and store in -20°C freezer as backup.

7 Add 50 µL of UA solution to a Microcon 30kDa filter unit. Avoiding the pellet, transfer the remaining 200 uL EDTA supernatant to the UA in the filter unit. Resuspend thoroughly to mix.

7.1 Spin at 14,000 rcf at 18°C for 15-18 minutes.

Extraction Day 1: Lysis and Denaturation

8 To the remaining pellet, add 30 µL of SDS-lysis buffer and mix by resuspension. Incubate on heat block for 5 minutes at 95°C.

9 Centrifuge at 14,000 rcf at 18°C for 10 minutes.

10 Add 200 µL of UA solution to the filter unit used in Step 7, followed by the pellet supernatant (~30 µL), avoiding any pellet debris, and resuspend to mix.

10.1 Centrifuge filter unit at 14,000 rcf at 18°C for 15-18 min until all liquid has passed through

10.2 Discard flow-through

11 Add another 200 µL of UA solution to the filter unit

11.1 Centrifuge filter unit at 14,000 rcf at 18°C for 15-18 min until all liquid has passed through

- 12** Place the remaining pellet tube in -20°C freezer for storage.

Extraction Day 1: Alkylation

- 13** Add 100 µL IAA solution (0.05 M) to the filter unit.
- 13.1** Mix at 300 rpm in the thermo-mixer for 1 min in the dark (cover with foil).
- 14** Incubate for 15-20 min in the dark
- 15** Centrifuge at 14,000 rcf at 18°C for 12-15 min until all liquid has passed through.
- 15.1** Discard flow-through in halogenated waste

Extraction Day 1: Wash steps

- 16** Add 200 µL of urea solution to the Microcon unit and centrifuge at 14,000 rcf for 15-18 minutes.

16.1 Repeat for a total of three washes of urea solution. Discard flow-through.

17 Add 100 μ L 0.05M TEAB to the Microcon unit and centrifuge at 14,000 rcf for 12-15 minutes.

17.1 Repeat twice for a total of three washes of TEAB solution.

Extraction Day 1: Digestion

18 Add 100uL of trypsin solution to each filter unit

18.1 Incubate overnight at 37C in the thermo-mixer at 300 rpm

Extraction Day 2

19 Transfer the Spin Filter to a new labeled collection tube.

20 Add 40 μ L of TEAB Solution. Centrifuge the Spin Filter at 14,000 rcf for 10 min. DO NOT DISCARD FLOW-THROUGH.

20.1 Repeat this step once.

- 21** Add 50 μ L 0.5 M Sodium Chloride Solution and centrifuge the Spin Filter at 14,000 rcf for 10 min.
- 22** The filtrate contains digested proteins. Acidify the filtrate with TFA to a pH below 3 (approximately 18 μ L of TFA will be needed).
- 23** Desalt using method of choice (e.g., StageTips or ZipTips).