VERSION 1
JUN 13, 2018

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.qx3dxqn

Protocol Citation: Amit Weiner 2018. Cloning guides to lentiCRISPR v2. **protocols.io** <https://dx.doi.org/10.17504/protocols.io.qx3dxqn>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
We use this protocol and it's working

Created: Jun 13, 2018

Last Modified: Jun 13, 2018

PROTOCOL integer ID:
13019

Cloning guides to lentiCRISPR v2 V.1

Amit Weiner¹

¹University of Toronto

Amit Weiner
University of Toronto

ABSTRACT

I have been struggling with cloning guide RNA sequences to the lentiCRISPR vector (<https://www.addgene.org/52961/>) for months now and have finally figured out a method that consistently works for me, so I felt like I should share this information with whomever is struggling as much as I did!

BEFORE START INSTRUCTIONS

Make Stbl3 chemically competent cells.

Vector preparation:

- 1 Digest the lentiCRISPRv2 vector:
3µg vector
2µl 10X Tango buffer (Thermo Fisher)
1µl 20mM DTT
1-1.5µl Esp3I (Thermo Fisher)
Water to 20µl

In a thermocycler:
37°C for 4 hours, inactivate at 65°C for 20 mins, keep at 4°C.
SKIP the alkaline phosphatase step.
- 2 Use a gel purification/PCR cleanup kit (Qiagen) **WITHOUT** running on a gel.
Optional: run ~200ng of the purified vector on a gel to verify digestion.

Guide insert preparation:

- 3 Anneal and phosphorylate gRNA oligos pair:
1µl of each oligo (100µM stock)
1µl 10X T4 ligation buffer (not PNK buffer)
0.5µl T4 PNK
Water to 10µl

In a thermocycler: 37°C for 30 mins, 95°C for 5 mins, ramp down to 25°C at 0.1°C/sec (or 5-6°C/min).
Optional: keep at 4°C.
- 4 Serially dilute the annealed oligos to 1:500

Ligation:

- 5 Out of ligation at a vector:insert molar ratios of 1:5, 1:10, 1:20, I found that 1:5 works best.

50ng vector
1.5µl 10X T4 ligation buffer (NEB)
1µl T4 ligase (NEB)
2µl diluted oligos (1:500)
Water to 15µl

Incubate at RT for 1-2 hours.

Transformation:

- 6 Transform 5µl of the ligation reaction to 50µl Stbl3 chemically competent cells.

If you incubate the Stbl3 cells at 30°C the colonies will be VERY small so look for them carefully.
Incubating them at 37°C didn't result in LTR recombination in my hands.

Colony PCR:

- 7 Replica plate colonies on a new LB-Amp plate prior to inserting the tip to 10µl water.
Mix well/ vortex
Boil at 98°C for 10 mins
- 8 Using primers upstream and downstream of the guide insert sequence, perform colony PCR:
F primer: gca tat acg ata caa ggc tgt tag aga ga
R primer: gag cca gta cac gac atc act t

	µl
10X buffer	2
10mM dNTPs	0.4
F primer (10µM)	0.3

R p r i m e r (1 0 u M)	0 . 3
B o i l e d c o l o n y	0 . 5
T a q p o l	0 . 1
d d H 2 O	1 6 . 4
T o t a l:	2 0

* Can be scaled up or down.

PCR program:

1	9 4 . C	5 m i n
2	9 4 . C	3 0 s e c
3	5 4 . C	1 m i n
4	7 2 . C	1 m i n / K b

	5	G o t o s t e p 2	X 3 0
	6	7 2 ° C	5 m in
	7	4 ° C	H o l d

- 9** Run on a gel -
product of positive colonies: 500 bp
product of negative colonies: 2500 bp

- 10** Send ~2 colonies per guide for sequencing with U6_fwd commercial primer.