VERSION 11

MAY 04, 2020

OPEN ACCESS

DOI:

dx.doi.org/10.17504/protocols.io.bfxfjpjn

External link:

<https://doi.org/10.1371/journal.pbio.2005840>

Protocol Citation: Mark Dewitt, Julia Wong, Beeke Wienert 2020. In vitro transcription of guide RNAs and 5'-triphosphate removal.

protocols.io

<https://dx.doi.org/10.17504/protocols.io.bfxfjpjn>

MANUSCRIPT CITATION:

Wienert B, Shin J, Zelin E, Pestal K, Corn JE (2018) In vitro-transcribed guide RNAs trigger an innate immune response via the RIG-I pathway. PLoS Biol 16(7): e2005840. doi: [10.1371/journal.pbio.2005840](https://doi.org/10.1371/journal.pbio.2005840)

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](https://creativecommons.org/licenses/by/4.0/), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

In vitro transcription of guide RNAs and 5'-triphosphate removal V.11

Mark Dewitt¹, Julia Wong¹, Beeke Wienert¹

¹UC BERKELEY-IGI

CornLab

Jacob E Corn

ETH Zurich

ABSTRACT

sgRNA template assembly, in vitro T7 transcription, and sgRNA column cleanup to remove 5'-triphosphate groups

Protocol status: Working
We use this protocol and it's working

Created: May 04, 2020

Last Modified: May 04, 2020

PROTOCOL integer ID:
36551

GUIDELINES

The primers used are: one long, variable oligo that carries the T7 promoter and desired guide sequence; an 82-nt constant oligo that carries the 3' end of the sgRNA; two short external primers for amplification.

Assembly Oligos:

T7FwdVar:

GGATCCTAATACGACTCACTATAG---guide-sequence---GTTT TAGAGCTAGAA

T7RevLong:

AAAAAAGCACCGACTCGGTGCCACTTTTTCAAGTTGATAACGGACTAGCCTTATTTT
AACTTGCTATTTCTAGCTCTAAAAC

Amplification Primers:

T7FwdAmp: GGATCCTAATACGACTCACTATAG

T7RevAmp: AAAAAAGCACCGACTCGG

Designing the guide sequence: The T7 transcript starts with the G before the dashes in the Fwd assembly oligo. If your target calls for a G at the 5' end of the guide, use the one already included in T7FwdVar design. If your target calls for a different base at the 5' end, put the whole guide sequence in T7FwdVar; there will be an extra G on the end that should have minimal effect, unless your guide is quite short.

Making the template: we have used the Phusion-HF DNA polymerase. Although the amplification primers have quite different T_m's, they work together fine.

MATERIALS

STEP MATERIALS

✂ DNase I (RNase-free) - 1,000 units **New England Biolabs Catalog #M0303S**

✂ Alkaline Phosphatase, Calf Intest (CIP) - 1,000 units **New England Biolabs Catalog #M0290S**

✂ HiScribe T7 High Yield RNA Synthesis Kit - 50 rxns **New England Biolabs Catalog #E2040S**

Design sgRNA and order PCR oligos.

- 1 Add the desired protospacer sequence to the T7FwdVar oligo and order the oligo from your favorite oligonucleotide supplier. There are many programs available for protospacer design that attempt to optimize on- and/or off-target activity. Which program is most useful depends upon many factors including type of editing, organism being edited, etc. Choice of protospacer design program is beyond the scope of this protocol.

The transcript will start with the bolded G just 5' of the dashes in the T7FwdVar oligo. T7 RNA polymerase requires a 5' G for proper transcript initiation. If your protospacer has a G at the 5' end, you can omit it from the T7FwdVar design to avoid duplication of the G. If your protospacer has a C, T, or A at the 5' end, add the whole protospacer sequence to T7FwdVar. In this case, there will be an extra G added to the 5' end of the protospacer, but literature indicates this will have minimal effect unless your guide is very short.

Primers:

T7FwdVar oligo (5'-GGATCCTAATACGACTCACTATAG**G**--protospacer sequence--GTTTTAGAGCTAGAA-3')

T7RevLong oligo (5'-

AAAAAAGCACCGACTCGGTGCCACTTTTTCAAGTTGATAACGGACTAGCCTTATTTAACTTGCTATTTCTAGCTCTAAAC-3')

T7FwdAmp primer (5'-GGATCCTAATACGACTCACTATAG-3')

T7RevAmp primer (5'-AAAAAAGCACCGACTCGG-3')

Generate in vitro transcription DNA template

- 2 For each T7FwdVar oligo you designed, set up the following PCR (total volume should be 20.0 µL). Make sure everything is RNase free and filter tips are used. Furthermore, wipe down everything (in every step of protocol) with RNase Away to ensure no contamination with RNase.

13.4 µl DEPC-treated H₂O

4.0 uL 5x Phusion HF Buffer

0.8 µl 10 mM dNTPs

0.4 µl T7FwdVar (1 µM)

0.4 µl T7RevLong (1 µM)
0.4 µl T7FwdAmp (100 µM)
0.4 µl T7RevAmp (100 µM)
0.2 µl Phusion HF DNA polymerase (2u/µl)

If making multiple sgRNA templates, prepare a master mix with all components except T7FwdVar. Include a no template control (omit T7FwdVar).

Primers:

T7FwdVar oligo (5'-GGATCCTAATACGACTCACTATAG--protospacer sequence--GTTTTAGAGCTAGAA-3')

T7RevLong oligo (5'-AAAAAAGCACCGACTCGGTGCCACTTTTTCAAGTTGATAACGGACTAGCCTTATTTAACTTGCTATTTCTAGCTCTAAAAC-3')

T7FwdAmp primer (5'-GGATCCTAATACGACTCACTATAG-3')

T7RevAmp primer (5'-AAAAAAGCACCGACTCGG-3')

In vitro transcription DNA template PCR

- 3 Run PCR:
- 95° 30 sec
 - 95° 10 sec
 - 57° 10 sec
 - 72° 10 sec
 - 15x steps 2-4
 - 72° 2 min
 - 4° hold

No PCR cleanup necessary at this point

In vitro T7 transcription

- 4 We like to use HiScribe T7 High Yield RNA Synthesis Kit but any T7 RNA synthesis kit should be fine.

Mix the following to make **20 µl** total T7 transcription mix

volume	reagent
2 µl	10x Buffer 1x
2 µl	ATP (100 mM), 10 mM
2 µl	GTP (100 mM), 10 mM

2 µl	CTP (100 mM), 10 mM
2 µl	UTP (100 mM), 10 mM
8 µl	DNA template from Step 3
2 µl	T7 RNA polymerase mix

HiScribe T7 High Yield RNA Synthesis Kit - 50 rxns **New England Biolabs Catalog #E2040**

- 5 Incubate transcription mix for ~18 hours (over night) at 37° in a thermocycler

18:00:00

37 °C

DNA template removal

- 6 Remove DNA template by adding 1 µl of RNase-free DNase; incubate 15 min at 37C in thermocycler

00:15:00 37C incubation

DNase I (RNase-free) - 1,000 units **New England Biolabs Catalog #M0303S**

37 °C

Removal of 5'-triphosphate groups

- 7 T7 in vitro transcription results in RNA carrying a 5'-triphosphate group. This triggers a RIG-I-mediated innate immune response in mammalian cells and can cause cell death, particularly in primary cells. We highly recommend treating your IVT sgRNA with Alkaline Calf Intestinal Phosphatase (CIP) before proceeding to the purification step. We found that CIP treatment must be rigorous to completely remove all 5-PPP groups from your RNA. However, CIP binds tightly to RNA and NEB recommends to only use the minimal amount needed.

Bring your IVT mix to a total volume of 88 µl with RNase-free water

- 8 Add 10µl of NEB buffer 2.1 (comes with the CIP enzyme)
Add 2µl (20 units) of CIP

Alkaline Phosphatase, Calf Intest (CIP) - 1,000 units **New England Biolabs Catalog #M0290S**

- 9 Mix well and incubate at 37C for 3h

03:00:00

37 °C

sgRNA purification

- 10** sgRNAs need to be purified before transfection. There are different methods one could purify their sgRNAs. We found that while SPRI bead clean-up of RNAs is quick and gives reliable yields (see older versions of protocol), SPRI bead purified sgRNAs still cause an elevated immune response even after CIP treatment. We therefore tested different column purification kits and found that column purification of sgRNAs completely eliminates the immune response after CIP treatment.

We use the Qiagen RNeasy Mini Prep Kit and follow the manufacturer's instructions with the following modifications:

Note

Yields of from column purification can be low as the sgRNAs are small and most kits are designed to bind longer RNAs. We found the Qiagen RNeasy kit works ok, but others recommend the miRNeasy kit from Qiagen. It might be worth trying a few different kits to optimize your yield.

- 11** Add 350 µl RLT Buffer to the sample
- 12** Add 550 µl 100% ethanol
- 13** Transfer ~500 µl to an RNeasy mini spin column; spin for 15 sec
Then transfer the remainder onto the same column; spin for 15 sec
- 14** Add 500 µl RPE Buffer; spin 15 sec
Repeated this wash step
- 15** Moved spin column to a new collection tube and spin for 1 min to dry the membrane completely

-
- 16** Move spin column to an RNase-free 1.5 ml microfuge tube
Add 20-30 μ l DEPC-treated H₂O; spin 1 min
Optional: Repeat the elution to collect any remaining RNA
 - 17** Measure your RNA concentration by Nanodrop or Qubit. Store sgRNAs at -80C