VERSION 1

MAY 14, 2018

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.p3tdqnn

External link:
www.caboscience.org

Protocol Citation: Etienne Laliberté 2018. Measuring specific leaf area and water content. **protocols.io** <https://dx.doi.org/10.17504/protocols.io.p3tdqnn>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](https://creativecommons.org/licenses/by/4.0/), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: In development
 We are still developing and optimizing this protocol.

Created: May 11, 2018

Last Modified: Apr 22, 2023

PROTOCOL integer ID:
 12115

Measuring specific leaf area and water content V.1

Etienne Laliberté¹

¹Université de Montréal

Plant Functional Ecology Lab

Canadian Airborne Biodiversity Observatory

Etienne Laliberté
 Université de Montréal

ABSTRACT

Here we describe the standardised protocol used by the [Canadian Airborne Biodiversity Observatory](https://caboscience.org/) (CABO) to measure leaf water content and specific leaf area, using the [WinFOLIA™](https://www.regentinstruments.com/) software ([Régent Instruments](https://www.regentinstruments.com/)). These leaf area and water measurements are done on a subset of leaves from the same bulk leaf sample used to measure [leaf spectral reflectance and transmittance](#). Briefly, after removing their petioles, fresh leaves are weighed, rehydrated for 6 h, scanned for total leaf area and weighed again; they are then oven-dried at 65 °C for 72 h, and weighed one last time. This allows us to measure leaf dry matter content and its complement, leaf water content, as well as leaf relative water content. Leaf area measurements are used to estimate specific leaf area, a key functional trait central to the leaf economics spectrum. Specific leaf area allows us to estimate equivalent water thickness and to convert concentrations of foliar biochemical constituents from a leaf mass to a leaf area basis.

GUIDELINES

Equipment

- Sartorius Secura 213-1S 1 mg (3 decimal places) balance or other similar balance
- Sartorius Secura 1102-1S 0.01 g (2 decimal places) balance or other similar balance
- Canon LiDE 220 portable scanner or other suitable flatbed scanner
- WinFOLIA™ leaf area software (Régent Instruments Inc.)
- Forced air drying oven
- Dessicator
- [RezChecker](#) color/resolution target (optional)

Consumables

- Paper towels
- Paper envelopes and/or bags
- Stapler and staples (for paper bags)
- Sealed plastic bags
- Weighing trays

Leaf Sample Selection And Preparation

- 1 Select a sub-sample of leaves from the same bulk fresh leaf sample on which [spectral reflectance and transmittance](#) was measured.

Note

The selected leaves do not have to be the same ones used for spectral measurements, but should be as similar as possible to those.

Note

Select enough leaves to entirely fill the scanner bed. Leaves larger than the scanner bed should be cut and scanned in multiple files.

- 2 Cut the petiole of each leaf that will be scanned.

Note

For a compound leaf, the petiole is the extension of the rachis beyond which there are no leaflets. The rachis should remain on the leaf, since it is the functional analogue of the midrib vein for a simple leaf.

Record Leaf Fresh Mass

- 3 Immediately weigh the selected leaves (with petioles removed) and **record the leaf fresh mass** (g).

Note

This fresh leaf mass should be done as close as possible to the spectral measurements; keep the fresh leaves in a sealed bag in which you have breathed into to prevent them from losing water.

Note

Use a 3-decimal place balance if possible. A 2-decimal place may be sufficient for very large leaves.

Leaf Rehydration

- 4 Store the selected leaves in a sealed plastic bag in which you have breathed into. Add a piece of damp paper towel (use deionised water).

Note

Label the sealed plastic bag with the sample ID and/or a barcode label.

- 5 Store the sealed sample in the dark, in the fridge (never a freezer) or a chilled cooler for **12 h**.

Record Leaf Rehydrated Mass

- 6 Gently pat dry the rehydrated leaves to remove surface water.

- 7 Weigh the rehydrated leaves as a whole and **record rehydrated leaf mass** (g).

Note

Use a 3-decimal place balance. A 2-decimal place balance can be sufficient for very large leaves.

Create Working Folder

- 8 Go to the shared 'leafscans' CABO Google Drive Folder for your project.

Note

If you do not yet have a shared Google Drive folder for your project, contact the CABO data manager to create one (etienne.laliberte@umontreal.ca or jeremy.goimard@umontreal.ca).

- 9 Create a new folder named YYYY-MM-DD-SiteID (without spaces) within that 'leafscans' folder.

Note

The 'Site ID' should be the same as the Site ID defined in the field for that site.

Note

This working folder is where the data file and all acquired images for that site on that day will be stored.

WinFOLIA Set-Up

- 10 Open WinFOLIA.

- 11 Choose the same settings as the last time WinFOLIA was run.

- 12 Select the scanner to use; it should start with WIA...

Note

The scanner drivers must be installed first. Choose the scanned starting with WIA...

- 13 Ensure that the scanner calibration file is loaded.

Note

If the scanner calibration file is not loaded, refer to the WinFOLIA manual to load it.

- 14 Ensure that the *Image > Acquisition Parameters...* are set as shown in the image below.

Note

The parameters shown are for the Canon LIDE 220 portable scanner used in the field, and may differ on another scanner.

Note

Although the leaf area analysis is done on greyscale images, **scan in color** at **150 dpi**.
For very small leaves, a higher resolution (e.g. 300 dpi) might be required.

- 15 Ensure that the *Analysis > Parameters...* are set as shown in the image below.

16 Ensure that the *Analysis > Measurements...* are set to *Total Area Only*.

Create New Data File

17 Create a new data file using *Data > New File...*

18 Save the data file as *YYYY-MM-DD-SiteID.txt* in the 'leafscans' CABO shared Google Drive folder for your project.

Leaf Scan

- 19 Position the leaves to fill the scanner bed:
 - position leaf apex at the top of the image
 - leave margins of scanned bed free
 - ensure leaves are not folded
 - ensure leaves do not overlap each other
- 20 Add the RezChecker target in the top left section of the image (optional; if target is available).

Note

This target can be used to calibrate the color and/or resolution of the image later on.

- 21 Acquire a scan.

- 22 Enter the Sample ID, and name of operator.

Note

The 'Sample ID' should be **exactly** the same sample ID of the bulk fresh leaf sample, as defined in the field.

- 23 Click anywhere on the scanned image to start the analysis on the whole image, or select a particular region for analysis, and **record the total leaf area** (cm²).

Note

The total leaf area (cm²) for that image gets automatically saved in the data file.

Note

If the leaf sample requires multiple scans, repeat steps 15-17 as many times as required. In that case, add an identifier at the end of the Sample ID (e.g. 4663504-A, 4663504-B).

- 24 Save the analysed image(s) in the Google Drive working folder.

- 25 Name the image file using the sample ID.

Record Leaf Dry Mass

- 26 Transfer the scanned leaves in a labelled paper envelope or small paper bag.

Note

Stape the envelope or paper bag to prevent leaves from falling out.

- 27 Dehydrate the leaves in forced air drying oven at **65 °C for 72 h**.

- 28 Ideally, cool the samples down to room temperature in a dessicator prior to weighing.

Note

If no dessicator is available, lower the drying oven temperature to room temperature but with forced air still on while samples are being weighed.

- 29 Weigh the dried leaves and **record leaf dry mass** (g).

Note

Use a 3 or 4-decimal-place balance, depending on sample size. A 2-decimal place balance might be sufficient for very large leaves.

Close Data File

- 30 Once all leaf samples for that site/day are scanned and analysed for area using WinFOLIA™, close the data file using *Data > Close File*.

Calculating Specific Leaf Area (SLA) and Leaf Mass per Area (LMA)

- 31 Specific leaf area (SLA; $\text{m}^2 \text{kg}^{-1}$) is calculated as:

$$\text{SLA} = (\text{LA} \div \text{LDM}) \div 10$$

where

LA is the total area of the leaf sample (cm^2)

LDM is the total leaf dry mass (g).

Leaf mass per area (LMA; g m^{-2}), the inverse of SLA, is calculated as:

$$\text{LMA} = \text{LDM} \div (\text{LA} \div 10\,000)$$

Calculating Leaf Dry Matter Content (LDMC) and Leaf Water Content (LWC)

- 32 Leaf dry matter content (LDMC; mg g^{-1}) is calculated as:

$$\text{LDMC} = (\text{LDM} \times 1000) \div \text{RLM}$$

where

LDM is the total leaf dry mass (g)

RLM is the rehydrated leaf mass (g)

Leaf water content (LWC; mg g^{-1}), the complement of LDMC, is calculated as:

$$\text{LWC} = 1000 - \text{LDMC}$$

Calculating Leaf Relative Water Content (RWC) and Equivalent Water Thickness (EWT)

- 33 The leaf relative water content (RWC; %) is expressed as:

$$\text{RWC} = [(\text{LFM} - \text{LDM}) \div (\text{RLM} - \text{LDM})] \times 100$$

where

LFM is the total leaf fresh mass (g),
LDM is the total leaf dry mass (g),
RLM is the rehydrated leaf mass (g).

Equivalent water thickness (EWT, g cm^{-2} , or $\text{cm}^3 \text{cm}^{-2} = \text{cm}$) is calculated as:

$$\text{EWT} = (\text{LFM} - \text{LDM}) \div \text{LA}$$

where

LA is the total leaf area (cm^2).

Note

The relative water content expresses the actual water content of a given amount of leaf relative to the amount of water it contains in its fully hydrated state. It is one measure of leaf water stress at the time when spectral measurements were made.

Equivalent water content expresses the amount of water per leaf area, also at the time when spectral measurements were made.