AUG 21, 2018

Phycocyanin Extraction from Synechocystis

Sebastian ST Triesch¹

¹Institute for Synthetic Microbiology

Axmann Lab

CyanoWorld

[1 more workspace](#) ↓

Sebastian ST Triesch

Institute for Synthetic Microbiology, HHU Düsseldorf

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.sr2ed8e

Protocol Citation: Sebastian ST Triesch 2018. Phycocyanin Extraction from Synechocystis. **protocols.io** <https://dx.doi.org/10.17504/protocols.io.sr2ed8e>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
 We use this protocol and it's working

Created: Aug 21, 2018

Last Modified: Aug 21, 2018

PROTOCOL integer ID:
 14874

Keywords: Phycocyanin, Synechocystis, Extraction

ABSTRACT

Extraction of Phycocyanin from Synechocystis liquid culture.

MATERIALS

MATERIALS

⊗ 0.5mm diameter glass beads **Scientific Industries, Inc. Catalog #SI-BG05**

⊗ Phosphate Buffered Saline **Thermo Fisher Scientific Catalog #28374**

- 1 Collect 1 ml *Synechocystis* liquid culture and spin it down at 14,000 g for 5 min. Discard the supernatant and keep the pellets cool.**

00:05:00 Centrifugation

- 2 **Fill** a **1.5 ml Eppendorf Tube** with **400 ml glass beads (~0.5 mm)** for each sample.
- 3 **Resuspend** the pellet from step 1 in **1 ml** PBS Buffer (pH = 7.4). Transfer the solution into the prepared 1.5 ml tubes filled with glass beads. Keep the solution cool.
- 4 Thoroughly **vortex** each sample for **1 min**. **Repeat** the process **five times**. The supernatant should become blue-green and clear.

00:01:00 Vortex

- 5 **Spin down** your vortexed sample for **5 min** at **3,000 g** at **4 °C**. **Transfer** the supernatant into a fresh **2 ml Eppendorf tube** and keep the supernatant cool.

00:05:00 Centrifugation

- 6 **Spin down** your supernatant again at **14,000 g** for **20 min** at **4 °C**.

00:20:00 Centrifugation

- 7 **Transfer** the supernatant into a cuvette. The supernatant should appear clearly blue at this stage. Measure the extinction at **620 nm**. Use PBS as a blank.