VERSION 3

JUL 24, 2019

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.5sig6ce

Protocol Citation: Research Cancer UK / Wellcome Gurdon Institute media kitchen 2019. Prepare NGM plates with fungizone. **protocols.io**
<https://dx.doi.org/10.17504/protocols.io.5sig6ce>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
We use this protocol and it's working

Created: Jul 24, 2019

Last Modified: Jul 24, 2019

PROTOCOL integer ID:
26154

Prepare NGM plates with fungizone V.3

Research Cancer UK / Wellcome Gurdon Institute media kitchen¹

¹Research Cancer UK / Wellcome Gurdon Institute

Cristian Riccio
University of Cambridge

ABSTRACT

Prepare NGM plates with fungizon

MATERIALS

MATERIALS

- Petri Dish P212121 Catalog #LI-PD01100
- Magnesium Sulfate Heptahydrate Certified AR for Analysis Fisher Chemical Fisher Scientific Catalog #M/1050/53
- Potassium Dihydrogen Orthophosphate Certified AR for Analysis Fisher Chemical Fisher Scientific Catalog # P/4800/53
- NGM medium Contributed by users
- fungizone Contributed by users
- Calcium chloride dihydrate for analysis EMSURE® ACSReag. Ph EurMerck Millipore Catalog #102382
- Cholesterol powder BioReagent suitable for cell culture ≥99% Sigma Aldrich Catalog #C3045

SAFETY WARNINGS

- Make sure you know how to use the autoclave before starting this protocol.

1

NGM+Fungizone_plates(1L).xls

2

Ingredient s			Quantity
NGM Media			1L
Cholesterol 5mg/ml		1ml	
1M CaCl ₂			1ml
1M MgSO ₄			1ml
1M KH ₂ PO ₄			25ml
Petri dish	30mm		as required
	50mm		as required
	90mm		as required
Fungizone	400 microlitres		1 microtube

3

First thing in the morning, melt 1L NGM in autoclave
Once melted, place in water bath set at 58°C, leave until cooled (-at least 2hours) normally left until the afternoon.
Set out the plates on bench before starting pouring process. Put melted NGM media on stirrer
Using 1ml Gilson add the Cholesterol, replace the lid and return to the bench to give a good stir to disperse all the cholesterol.

	Add the KH ₂ PO ₄ using sterile 50ml syringe and 0.22µm filter.
	Stir for a few seconds until well mixed. Add Fungizone ensuring all is added to the NGM.
	Dispense media using a peristaltic pump. Add 4.20ml in 30mm plates, 9.00ml in 50mm plates, 4.50ml in 6 well plates and 2.5ml in 12 well plates. When set stack upside down in plastic trays.