MAR 28, 2019

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.zksf4we

Protocol Citation: Magdalena M Julkowska 2019. ROS staining for Arabidopsis (green fluorescent stain). **protocols.io**
<https://dx.doi.org/10.17504/protocols.io.zksf4we>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
 We use this protocol and it's working

Created: Mar 28, 2019

Last Modified: Mar 28, 2019

PROTOCOL integer ID:
 21874

Keywords: ROS, Arabidopsis, fluorescent stain

ROS staining for Arabidopsis (green fluorescent stain)

Magdalena M Julkowska¹

¹Boyce Thompson Institute

Magdalena M Julkowska
 Boyce Thompson Institute

ABSTRACT

This protocol is adapted from two publications describing fluorescent staining for ROS - [Shin et al., 2005](#) and [Orman-Ligeza et al. 2016](#) (citing Shin)

MATERIALS

MATERIALS

✕ Murashige & Skoog medium including B5 vitamins [Duchefa Biochemie Catalog #M0231](#)

✕ Costar® 6 Well Clear TC-Treated Multiple Well Plates, Individually Wrapped, Sterile [Westnet Catalog #3516](#)

✕ CM-H2DCFDA Thermo Fisher Scientific Catalog #C6827

BEFORE START INSTRUCTIONS

prepare sterile MS medium:

- 1/2 MS
- 0.5% sucrose
- 0.1% MES buffer
- pH 5.8 with KOH

Autoclave

prepare CM-H2DCFDA according to the supplier instructions

- 1 Sterilize the seedlings, germinate and transfer to for e.g. salt stress medium as described in the "Quantification of salt-induced changes in Root System Architecture in Arabidopsis" protocol - [dx.doi.org/10.17504/protocols.io.zkqf4vw](https://doi.org/10.17504/protocols.io.zkqf4vw)
- 2 Transfer the seedlings from agar plates into nutrient solution that is the same as agar plate composition (but without Dashin agar). You can use 24/12/6 well-plates - this will depend on your final seedlings size
- 3 After transferring the seedlings to liquid medium add DCF-DA so that the final concentration of the DCF-DA in the incubation medium is 50 μ M
- 4 Wrap the well plate in aluminium foil (DCF-DA is light sensitive) and let the samples incubate for 30 min with gentle shaking.
- 5 Wash the seedlings with medium without DCF-DA
- 6 Image the stain using fluorescence microscopy:
 - 460–500 nm bandpass excitation
 - 510– 560 nm bandpass emission