OCT 21, 2019

RPA DNA Amplification using TwistAmp™ Basic

Luc Gabel¹, Théo Nass¹

¹EPFL - EPF Lausanne

iGEM EPFL

Dana Mozaffari

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.8erhtd6

Protocol Citation: Luc Gabel, Théo Nass 2019. RPA DNA Amplification using TwistAmp™ Basic.
protocols.io
<https://dx.doi.org/10.17504/protocols.io.8erhtd6>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
 We use this protocol and it's working

Created: Oct 18, 2019

Last Modified: Oct 21, 2019

PROTOCOL integer ID:
 28849

ABSTRACT

This protocol describes the procedure to perform an RPA DNA Amplification using the TwistAmp™ Basic

MATERIALS

Prime r-free rehydration buffer	29.5 µl
Prime r A (10µM)	2.4 µl
Prime r B (10µM)	2.4 µl
Template (DNA) *	5 µl
Nucle ase-free water	8.2 µl
Total	47.5 µl

Quantities for preparation of a 50 µl RPA reaction using TwistAmp™ Basic

* TwistAmp™ Basic RPA reactions are very sensitive, it is recommended to use low copy numbers. Solutions with a concentration over 10 000 copies/µl should not be opened in the area you set up your RPA as they might contaminate all your reactions.

- 1 Prepare the RPA pellet rehydration solution in a 1.5 ml tube following the table in the Materials section.

If possible do a Master Mix that will then be divided.

- 2 Vortex and spin briefly.
- 3 For each sample, transfer the entire volume (47.5 μ l) to a reaction pellet. Pipette up and down until the pellet is fully resuspended.
- 4 Add 2.5 μ l of 280mM MgOAc to the cap of each reaction tube. MgOAc will make the reaction start, it is added to the cap so that all reactions start simultaneously when spun down.
- 5 Do a short spin to make the MgOAc drop fall down into the tube, vortex briefly and do another quick spin.
- 6 Incubate at 39°C for 20 min
For low copy numbers, incubate 4 minutes, vortex and spin briefly and incubate again for 16 minutes.
- 7 After the incubation, purify the sample if you want to run the RPA product on an agarose gel.

PCR purification kits work well, but since RPA primers can be very long (60+ bp), a high cutoff is recommended.

Do not open post-amplification RPA reactions in the same workspace as you set up pre - amplification RPA, or take appropriate measures to limit DNA contamination.