VERSION 1

JAN 13, 2020

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.2ivgce6

Protocol Citation: Robert Policastro, Gabe Zentner 2020. STRIPE-seq library construction. [protocols.io](https://dx.doi.org/10.17504/protocols.io.2ivgce6) <https://dx.doi.org/10.17504/protocols.io.2ivgce6>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](https://creativecommons.org/licenses/by/4.0/), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
 This protocol has been used for the construction of yeast and human STRIPE-seq libraries in our lab.

Created: May 01, 2019

Last Modified: Jan 13, 2020

PROTOCOL integer ID:
 22837

STRIPE-seq library construction V.1

Robert Policastro¹, Gabe Zentner¹

¹Indiana University

Gabe Zentner
 Indiana University

ABSTRACT

Accurate mapping of transcription start sites (TSSs) is key for understanding transcriptional regulation; however, current protocols for genome-wide TSS profiling are laborious and expensive. We present Survey of TRanscription Initiation at Promoter Elements with high-throughput sequencing (STRIPE-seq), a simple, rapid, and cost-effective protocol for sequencing capped RNA 5' ends from as little as 50 ng total RNA. Including depletion of uncapped RNA and bead cleanups, a STRIPE-seq library can be constructed in approximately 4 hours.

MATERIALS

MATERIALS

- ✂ Terminator 5-Phosphate-Dependent Exonuclease **Lucigen Catalog #TER51020**
- ✂ RNAClean XP **Beckman Coulter Catalog #A63987**
- ✂ 5M Betain **Thermo Fisher Scientific Catalog #AAJ77507UCR**
- ✂ KAPA HiFi HotStart ReadyMix **Roche Catalog #KK2601**
- ✂ Sorbitol **Dot Scientific Catalog #DSS23080-500**
- ✂ Trehalose **MP Biomedicals Catalog #0210309705**
- ✂ dNTPs 10 µM each **VWR Scientific Catalog #97063-232**
- ✂ SuperScript II Reverse Transcriptase **Thermo Fisher Scientific Catalog #18064014**
- ✂ RNA ScreenTape **Agilent Technologies Catalog #5067-5576**
- ✂ High Sensitivity D5000 ScreenTape **Agilent Technologies Catalog #5067-5592**

Keywords: TSS,
transcription, transcription
start site

Prepare Total RNA

- 1 Check RNA quality and concentration on an Agilent TapeStation using an RNA ScreenTape.

15m

Expected result

You should have at least 50 to 200 ng of total RNA at a concentration of at least 30 to 125 ng/ μ l. Your total RNA should also not be highly degraded, as measured by the quality of the rRNA peaks.

Equipment

TapeStation	NAME
Agilent	BRAND
G2991AA	SKU
https://www.agilent.com/en/product/tapestation-automated-electrophoresis/tapestation-instruments/4200-tapestation-system-228263	LINK

Terminator Exonuclease (TEX) Digestion of Uncapped RNA

- 2 **Prepare TEX Reaction.** TEX preferentially degrades uncapped RNA, thus reducing the amount of rRNA and degraded mRNA fragments in the sample.

- 2.1 Create TEX master mix (per sample).

3m

1. 0.2 μ L Terminator Exonuclease .
2. 0.2 μ L Terminator Exonuclease Reaction Buffer A .

Vortex and spin down to mix.

2.2 Prepare TEX reactions in 0.2 mL PCR tubes. 5m

1. 0.3 μ L TEX Master Mix .
2. Up to 1.6 μ L Total RNA .
3. Nuclease free water to 2 μ L total reaction volume.

Vortex and spin down to mix.

3 Incubate the TEX reactions in thermal cycler. 1h

1. 30 °C for 01:00:00 .
2. 4 °C Hold .

Note

This is a good time to prepare the Reverse Transcription Oligo (RTO) annealing and Template Switching Reverse Transcription (TSRT) reaction mixtures from steps 4.1 and 5.1.

Template Switching Reverse Transcription

4 Anneal reverse transcription oligo (RTO) to RNA. STRIPE-seq primes RT using a random pentamer with the full length TrueSeq R2 adapter (including the barcode) attached to it.

4.1 Prepare one RTO annealing mix per sample. 5m

1. 1.5 μ L Sorbitol/Trehalose Solution .
2. 1 μ L Reverse Transcription Oligo (RTO) 1M 10 micromolar (μ M) . Each sample should have its own unique barcode.

3. 0.5 μL dNTPs IM1 10 micromolar (μM) Each .

Vortex and spin down to mix.

- 4.2 Add 2 μL TEX Reaction (from step 3) to 3 μL RTO Annealing Mixture (from step 4.1) in 0.2 mL PCR tube. Vortex and spin down to mix.

- 4.3 Incubate RTO annealing mixture in thermal cycler.

1. 65 °C 00:05:00 .
2. 4 °C 00:02:00 .
3. 4 °C Hold .

- 5 **Prepare template switching reverse transcription (TSRT) reactions.** The process of template switching reverse transcription enriches for the 5' end of capped RNA in the final library.

- 5.1 Prepare TSRT reaction master mix (per sample).

1. 2 μL Betaine IM1 5 Molarity (M) .
2. 2 μL 5X SuperScript II First Strand Buffer .
3. 0.5 μL DTT IM1 0.1 Molarity (M) .
4. 0.5 μL SuperScript II Reverse Transcriptase .

Vortex and spin down to mix.

Note

Add reverse transcriptase to master mix just prior to aliquoting to samples.

- 5.2 Add 5 μL TSRT Master Mix (from step 5.1) into the 5 μL TSO Annealing Reaction from step 4.3. Vortex and spin down to mix.

6 TSRT.

- 6.1 First half of TSRT reaction.

1. 25 °C 00:10:00
2. 42 °C 00:05:00

Note

Move on to step 6.2 immediately after the end of step 6.1.

6.2 Adding TSO. Keep the samples in the thermal cycler while adding the TSO.

3m

1. 0.25 µL TSO IM1 400 micromolar (µM)
2. Quickly vortex and spin down tubes to mix, and immediately place tubes back in thermal cycler.

Note

Move on to step 6.3 immediately after end of step 6.2.

6.3 Second half of TSRT reaction.

30m

1. 00:25:00 42 °C
2. 00:10:00 70 °C
3. 4 °C Hold

Note

This is a good time to prepare the library PCR master mix in step 8.1.

7 Cleanup of TSRT product.

20m

1. Transfer the TSRT product from step 6.3 into 0.5 mL tubes.
2. Pipette 8 µL RNAClean XP Beads up and down 10 times into 10 µL TSRT Reaction from step 6.3.
3. Incubate for 00:05:00 at Room temperature.
4. Place tubes on magnetic rack and incubate for 00:05:00 at Room temperature.
5. Discard supernatant. Leave ~ 1 µL in tube to avoid sucking up beads.
6. While tube is still on rack, wash beads with 175 µL 70% Ethanol, and immediately discard wash without incubation.
7. Air dry beads for 00:05:00 at Room temperature.
8. Resuspend beads in 12 µL Nuclease Free Water, and incubate on magnetic rack for 00:01:00 at Room temperature.

9. Transfer 11 μ L Supernatant into new 0.2 mL PCR tube.

Library PCR

8 Prepare library PCR reaction.

8.1 Create library PCR master mix (per sample).

5m

1. 12.5 μ L 2X KAPA HiFi HotStart ReadyMix
2. 0.75 μ L Forward Library Oligo (FLO) 10 micromolar (μ M)
3. 0.75 μ L Reverse Library Oligo (RLO) 10 micromolar (μ M)

Vortex and spin down to mix.

8.2 Add 14 μ L Library PCR Master Mix (from step 8.1) into 11 μ L Cleaned TSRT Product (from step 7). Vortex and spin down to mix.

2m

9 Run library PCR reaction.

45m

Initial Denaturation:

- 95 °C 00:03:00

16-20 cycles:

- 98 °C 00:00:20
- 63 °C 00:00:15
- 72 °C 00:00:45

Final Extension:

- 72 °C 00:02:00
- 4 °C Hold

10 Size selection of final library. SPRI bead size selection is used to remove fragments that are outside the ideal size for illumina sequencing.

10.1 Removal of small fragments.

20m

1. Transfer library PCR product from step 9 into 0.5 mL tube.

2. Pipette 16.3 µL RNAClean XP Beads up and down 10 times into 25 µL Library PCR Product from step 9.
3. Incubate for 00:05:00 at Room temperature.
4. Place tubes on magnetic rack and incubate for 00:05:00 at Room temperature.
5. Discard supernatant. Leave ~ 2 µL in tube to avoid sucking up beads.
6. While tube is still on rack, wash beads with 175 µL 70% Ethanol, and immediately discard wash without incubation.
7. Air dry beads for 00:05:00 at Room temperature.
8. Resuspend beads in 17 µL Nuclease Free Water, and incubate on magnetic rack for 00:01:00 at Room temperature.
9. Transfer 15 µL Supernatant to new 0.5 mL tube.
10. **Optional:** Reserve 1 µL Remaining Supernatant from beads if you would like to see library size distribution after removing small fragments.

10.2 Removal of large fragments.

40m

1. Pipette 8.3 µL RNAClean XP Beads up and down 10 times into 15 µL Cleaned Product from step 10.1.
2. Incubate for 00:10:00 at Room temperature.
3. Place tubes on magnetic rack and incubate for 00:10:00 at Room temperature.
4. Transfer 22 µL Supernatant to new tube.
5. Pipette 22 µL RNAClean XP Beads up and down 10 times into 22 µL Supernatant from previous step.
6. Incubate for 00:05:00 at Room temperature.
7. Place tubes on magnetic rack and incubate for 00:05:00 at Room temperature.
8. Discard supernatant. Leave ~ 2 µL in tube to avoid sucking up beads.
9. While tube is still on rack, wash beads with 175 µL 70% Ethanol, and immediately discard wash without incubation.
10. Air dry beads for 00:05:00 at Room temperature.
11. Resuspend beads in 16 µL Nuclease Free Water, and incubate on magnetic rack for 00:01:00 at Room temperature.
12. Transfer 15 µL Supernatant to new tube.

Library Quality Control

- 11 Run final libraries on the Agilent TapeStation using a High Sensitivity D5000 ScreenTape.

15m

Expected result

Final libraries should be distributed between 250 to 750 bp with a total library amount of 25 to 100 ng.