VERSION 3

FEB 14, 2019

OPEN ACCESS

DOI:

dx.doi.org/10.17504/protocols.io.x45fqy6

Protocol Citation: Binnypreet Kaur, Drahomíra Faktorová, Julius Lukeš 2019.

Transfection of constructs in diplomemids to enhance the HR pathway, using RS-1 (3-(benzylamino) sulfonyl)-4-bromo-N-(4-bromophenyl) benzamide).. **protocols.io** <https://dx.doi.org/10.17504/protocols.io.x45fqy6>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: In development
We are still developing and optimizing this protocol

Created: Feb 14, 2019

Last Modified: Feb 14, 2019

Transfection of constructs in diplomemids to enhance the HR pathway, using RS-1 (3-(benzylamino) sulfonyl)-4-bromo-N-(4-bromophenyl) benzamide). V.3

Binnypreet Kaur¹, Drahomíra Faktorová ², Julius Lukeš ³

¹[Institute of Parasitology Czech Academy of Sciences Faculty of Sciences University of South Bohemia Czech Republic];

²[Institute of Parasitology Czech Academy of Sciences Faculty of Sciences University of South Bohemia Czech Republic];

³[Institute of Parasitology Czech Academy of Sciences Faculty of Sciences University of South Bohemia Czech Republic] [Canadian Institute for Advanced Research Toronto Canada]

Protist Research to Optimize Tools in Genetics (PROT-G)

Julius Lukes

Binnypreet Kaur

1 Institute of Parasitology, Biology Centre, Czech Academy o...

ABSTRACT

RS-1 (RAD51-stimulatory compound 1) is a stimulator of homologous recombination (HR) protein RAD51

- 1 Step 1: Count the cells and plan to 1 nucleofection with 5×10^7 cells for each construct.
- 2 Step 2: Harvest the cells by centrifugation at 1300xg for 5 min at room temperature in Swing Bucket Rotor.
- 3 Step 3: Resuspend the cell pellet in 100ul of AMAXA Human T- cell solution at 4C (from refrigerator combine 81.8ul of Human T-cell nucleofector solution + 18.2ul Supplement).
- 4 Step 4: Add 5-10ug of (PCR) (linearized DNA) along with 0.3 uM RS-1 enhancer into the cuvette (resuspend in 10ul of H₂O).
- 5 Step 5: Put everything into the cuvette, close the cap and place in the electroporator, cuvette should only fit in one direction, but metal sides should face towards you.
- 6 Step 6: Press for the Program X-001 to electroporate and repeat the same as mentioned in transformation protocol.
- 7