OCT 03, 2019

WarmStart LAMP®

Kenneth Schackart¹

¹University of Arizona

Yoon Lab

Kenneth Schackart
University of Arizona

ABSTRACT

How to run nucleic acid amplification using the Warm-Start LAMP kit.

Each reaction produces 25 µL.

For the original protocol, look at: LAMP Protocol.pdf .

*I have not verified the details of this protocol, I would like to remove it, but I cannot since it has been forked.

If you would like to use this protocol, I would recommend using the PDF above instead.

GUIDELINES

Gloves must be worn at all times.

Use all precautions to avoid contamination when making reaction mixture.

Always pipette mix each reagent in aliquot before pipetting.

MATERIALS

MATERIALS

WarmStart LAMP Kit (DNA and RNA) - 100 rxns **New England Biolabs Catalog**
#E1700S

DNase/RNase free distilled water **Thermo Fisher Scientific Catalog**
#10977023

- 70% ethanol solution in DI water
- RNAway
- WarmStart LAMP Master Mix (2x)
- LAMP primer mix (10x)
- Target DNA or RNA
- RNase free water

OPEN ACCESS

DOI:
dx.doi.org/10.17504/protocols.io.xppfmmn

Protocol Citation: Kenneth Schackart 2019. WarmStart LAMP®. **protocols.io**
<https://dx.doi.org/10.17504/protocols.io.xppfmmn>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](https://creativecommons.org/licenses/by/4.0/), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Other
Refer to the actual protocol instead. I had to publish this to free up space in Yoon Lab.

Created: Feb 01, 2019

Last Modified: Oct 03, 2019

PROTOCOL integer ID:
19919

Prepare Work Area

- 1 Spray entire work area with 70% EtOH including pipettes, tip holder used for holding PCR tubes, and work surface. Wipe with a paper towel.
- 2 Spray entire work area with RNAway.

Gather Materials

- 3 Take styrofoam container to Marley 527 (directly across from Marley 509) and fill halfway with ice.
- 4 Set PCR tube holder on ice, and allow to cool for 00:03:00 .
- 5 Transfer Master Mix, primers, RNase free water, and target tubes from freezer to PCR tube holder on ice.
- 6 Allow reagents to thaw on ice
- 7 Carefully obtain (2) 0.2 mL PCR tubes. Label one with "NTC" and the other "TARG". These will be your reaction vessels.

Note

To avoid contamination when grabbing PCR tubes, only touch the outside of tubes. Avoid touching the inside of the caps of other tubes in this process. This is critical.

8 Vortex mix all reagents for approximately 00:00:05 .

9 Spin down all reagents for approximately 00:00:05 .

Prepare Reaction

10 Using a 2-20 μL pipette, transfer 9 μL RNase free water into the **TARGET** reaction vessel.
Using a 2-20 μL pipette, transfer 10 μL RNase free water into the **NTC** reaction vessel.

11 Using a 2-20 μL pipette, transfer 12.5 μL WarmStart Master Mix into each reaction vessel.

12 Using a 0.5-10 μL pipette, transfer 2.5 μL Primer to each reaction vessel.

Note

Primer will depend on what your target is. For E. Coli OH157, the primer tube is labelled with an 'F'.

13 Using a 0.5-10 μL pipette, transfer 1 μL Target into the **TARGET** reaction vessel.

14 Vortex mix the reaction mixture.

- 15 Spin down reaction mixture.

Run LAMP Reaction

- 16 Place reaction vessels into thermocycler.
- 17 Turn on thermocycler
- 18 Hit PROCEED to select a reaction cycle.
- 19 Scroll using the '<' and '>' keys to get to LAMP3.
- 20 Press PROCEED to begin