

Sep 04, 2018

Extracting plasmid DNA from Agrobacterium with the Bioline ISOLATE II Plasmid Mini Kit

DOI

dx.doi.org/10.17504/protocols.io.s8fehtn


James P B Lloyd¹, Ryan Lister¹

¹University of Western Australia



James P B Lloyd

University of Western Australia



OPEN  ACCESS



DOI: dx.doi.org/10.17504/protocols.io.s8fehtn

Protocol Citation: James P B Lloyd, Ryan Lister 2018. Extracting plasmid DNA from Agrobacterium with the Bioline ISOLATE II Plasmid Mini Kit. [protocols.io](https://dx.doi.org/10.17504/protocols.io.s8fehtn) <https://dx.doi.org/10.17504/protocols.io.s8fehtn>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](https://creativecommons.org/licenses/by/4.0/), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working

We use this protocol and it's working

Created: September 04, 2018

Last Modified: September 04, 2018

Protocol Integer ID: 15335

Keywords: Agrobacterium, plasmid, mini-prep



Abstract

To extract plasmid DNA from *Agrobacterium*, to confirm the correct plasmid has been taken-up, this protocol allows you to directly perform a mini-prep on transformed *Agrobacterium*, digest this DNA and visualize it on a gel. This is without the need of rescuing the plasmid in *E. coli* or genotyping with PCR. This protocol using the commercially available Bioline ISOLATE II Plasmid Mini Kit, designed for use with *E. coli*. The standard protocol this is modified from is available

here: https://www.bioline.com/au/downloads/dl/file/id/1219/isolate_ii_plasmid_mini_kit_protocol.pdf

Materials

MATERIALS

 ISOLATE II Plasmid Mini Kit **Bioline Catalog #BIO-52057**

Safety warnings

- ⚠ Please check the MSDS information for the ISOLATE II Plasmid Mini Kit: https://www.bioline.com/au/downloads/dl/file/id/2807/isolate_ii_plasmid_mini_kit_msds.pdf

Before start

Ensure RNase A has been added to Resuspension Buffer P1. Pre-warm the required amount of PW1 to 50-55 °C before starting the extration. Ensure Ethanol has been added to PW2.




Harvest bacterial cells

- 1 Pellet 3 ml of a saturated *Agrobacterium* LB culture with appropriate antibiotics for 30s at 11,000 x g.



Expected result

Typical pellet after spinning down 3 ml of 24 hour grown Agrobacterium.





Note

I grew *Agrobacterium* in 5 ml of LB with appropriate antibiotics for 24 hours at 29 °C.

Spinning the 3 ml down can be done in two steps of 1.5 ml.


- 2 Discard supernatant and remove as much liquid as possible.

Lyse cells

- 3 Add 250µl Resuspension Buffer P1 and resuspend cell pellet by pipetting up and down.

- 4 Add 250µl Lysis Buffer P2. Mix gently by inverting tube 6-8 times. Incubate at room temperature for up to 5 min or until lysate appears clear.

Note: Do not vortex to avoid shearing genomic DNA

 00:05:00 Lysis

- 5 Add 300µl Neutralization Buffer P3. Mix thoroughly by inverting tube 6-8 times.

Note: Do not vortex to avoid shearing genomic DNA

Clarification of lysate

- 6 Centrifuge 10 min at max speed at room temperature.

Note

The max speed on the centrifuged I used was 20817 x g but faster is probably not a bad thing.

The pellet is very glopy (snot-like) so a long, fast spin at this stage is vital to being able to get the supernatant.



Expected result

This is the very snot-like pellet. Ensure you do not disturb it when you take the supernatant.





Bind DNA

- 7 Bind DNA Place ISOLATE II Plasmid Mini Spin Column in a 2ml Collection Tube. Pipette (do not decant) a maximum of 750µl (usually less) of clarified sample supernatant onto column.
Centrifuge 1 min at 11,000 x g and discard flow-through.

Wash silica membrane

- 8 Add 500µl Wash Buffer PW1 preheated to 50°C. Centrifuge 1 min at 11,000 x g. Discard flow-through and reuse Collection Tube.

Note

The use of PW1 is considered optional for some E. coli strains but is essential for extracting plasmid from Agrobacterium as it contains many nucleases, which PW1 is used to remove.

I actually warmed it up to 55 °C, but I am sure the manual's recommended 50 °C will work just the same.

- 9 Add 600µl Wash Buffer PW2 (supplemented with ethanol). Centrifuge 1 min at 11,000 x g. Discard flow-through and reuse Collection Tube.

Dry silica membrane

- 10 Centrifuge 2 min at 11,000 x g, to remove residual ethanol. Place ISOLATE II Plasmid Mini Spin Column in a 1.5ml microcentrifuge tube.

Elute DNA

- 11 Add 30-50µl Elution Buffer P, nuclease-free water or TE buffer directly onto center of silica membrane. Incubate at room temperature for 1 min.



00:01:00 Elution incubation



12 Centrifuge 1 min at 11,000 x g.

Restriction enzyme digestion

13 The DNA is now very dilute so it would be a good idea to use 20 μ l in a typical restriction enzyme digest. This is usually much less than you would use from a prep from *E. coli*.