

Aug 09, 2018

Version 1

# C Leaf Punch DNA Extraction V.1

DOI

dx.doi.org/10.17504/protocols.io.sgpebvn

Alex Rajewski<sup>1</sup>, Cecilia McGregor<sup>2</sup>

<sup>1</sup>University of California, Riverside; <sup>2</sup>University of Georgia



## Alex Rajewski

University of California, Riverside

# Create & collaborate more with a free account

Edit and publish protocols, collaborate in communities, share insights through comments, and track progress with run records.

Create free account

OPEN ACCESS



DOI: https://dx.doi.org/10.17504/protocols.io.sgpebvn

**Protocol Citation:** Alex Rajewski, Cecilia McGregor 2018. Leaf Punch DNA Extraction. **protocols.io** <a href="https://dx.doi.org/10.17504/protocols.io.sgpebvn">https://dx.doi.org/10.17504/protocols.io.sgpebvn</a>

### **Manuscript citation:**

Edwards et al. Nucleic Acids Research 19(6): 1349

**License:** This is an open access protocol distributed under the terms of the **Creative Commons Attribution License**, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working

We use this protocol and it's working

Created: August 08, 2018

Last Modified: August 09, 2018

Protocol Integer ID: 14575


**Keywords:** genomic dna extraction protocol for fresh leaf, genomic dna extraction protocol, seed tissue in many plant species, extraction, dna, typical yeilds of dna, many plant species, fresh leaf, seed tissue, exceptional lengths of dna, routine pcr

### **Abstract**

This is a quick (and very cheap) genomic DNA extraction protocol for fresh leaf or seed tissue in many plant species. It should be use preferably for extractions that do not require exceptional lengths of DNA, and is suitable for routine PCR, sanger sequencing, and restriction digests. The protocol is modified from Edwards *et al. Nucleic Acids Research* 19(6): 1349, and has been adapted since then by Zach King, Jonathan Serrano, and Cecilia McGregor. Typical yeilds of DNA are  $\sim 200 \text{ng}/\mu\text{L}$ .

### **Materials**

### STEP MATERIALS



Ethylenediaminetetraacetic acid disodium salt dihydrate Merck MilliporeSigma (Sigma-Aldrich) Catalog #E4884

### Protocol materials

Ethylenediaminetetraacetic acid disodium salt dihydrate Merck MilliporeSigma (Sigma-Aldrich) Catalog #E4884

Ethylenediaminetetraacetic acid disodium salt dihydrate Merck MilliporeSigma (Sigma-Aldrich) Catalog #E4884

Ethylenediaminetetraacetic acid disodium salt dihydrate Merck MilliporeSigma (Sigma-Aldrich) Catalog #E4884

# Troubleshooting

# Safety warnings

•

All reagents listed here can be disposed of in the sink.



# Before start

Collect and freeze tissue before starting, and make up the stock solutions in advance.




## Preparation

Collect young leaf (the size of a penny) into a 2 mL Eppendorf tube. Store tubes at -80°C until extraction.

## **Solution Preparation**


2 Make 500mL of a 1M Tris solution by dissolving 78.8g of Tris-HCl into 500mL of DI water, adjusting the pH to 8 with HCl, and autoclaving.




#### Note

This recipe has approximate volumes for HCl and water. Also, confirm that you are using Tris-HCl and not Tris-Base. Either is fine, but substitutions will change the mass of Tris needed and also alter the starting pH of the solution.

3 Make a 5M NaCl solution by dissolving 146g of NaCl in ~400mL of DI water, bringing to 500mL, and autoclaving.



Make a 0.5M EDTA solution by dissolving 93.05q of EDTA in ~400mL of DI water. Adjust the pH to 8 by adding ~20g of NaOH. Bring to 500mL and autoclave.



4 93.05 q EDTA

■ 3.05 q EDTA

■ 4.05 q EDTA

20 q NaOH

∆ 500 mL DI water

#### Note

The disodium salt of EDTA will not dissolve until the pH is near 8.

5 Make a 10% SDS solution by dissolving 50g of sodium dodecyl sulphate in ~400mL of DI water. Heat it to 65°C to dissolve, and then bring to 500mL. There is no need to



autoclave this solution.

4 50 g SDS

■ 50 g SDS

∆ 500 mL DI water

6 Prepare the Edward's Buffer by adding the following compenents, bringing to 1L with DI water, and then autoclaving.

4 50 mL 5M NaCl

■ The state of the st

4 50 mL 0.5M EDTA

△ 50 mL 10% SDS

## **Grind Tissue**

- 7 Snap freeze the tubes in a dewar of liquid nitrogen (LN2).
- 8 Freeze a plastic tube wrack by pouring LN2 into it until the LN2 no longer evaporates.
- 9 Quickly remove an Eppendorf tube with the leaf tissue from the dewar, warm the tube hinge with your fingers to prevent it from breaking, open the tube, and place it in one of the LN2-containing wells. Make sure that no LN2 gets into the tube. Using a plastic pestle, grind the tissue to a fine powder, transferring the tube to a new well every ~10 seconds to prevent it from thawing. Close the tube, return it to the dewar, and process the next sample.

# Lysis

10 Prepare 750µL of 60% Edwards buffer and 40% 5M NaCl for each tube.

450 μL Edward's Buffer

Δ 300 μL 5M NaCl

11 Add 750µL of this Edwards/NaCl mixture to each tube, vortex, and place at 60°C for 30 minutes, inverting 2-3 times during the incubation to mix.

© 00:30:00 at 60°C with occasional inversion

12 Centrifuge the tubes for 5 min at 13,000 rpm. During this spin, proceed to the next step.

(\*) 00:05:00 spin at 13,000rpm



# Precipitation

- While the tube are spinning, add  $500\mu$ L of 100% isopropanol into a new tube. This is the tube you will store the samples in. Clearly label it with your initials, the sample ID and date on side, and the sample ID on the lid.
  - Δ 500 μL isopropanol
- Once the tubes are done spinning, transfer 500µL of the supernatant into the isopropanol tube, and gently invert several times to mix.

#### Note

During the transfer to not disturb the pellet at the bottom of the tube.

During the inversion, you may see your DNA precipitate as a white-ish, wispy cloud that that looks like snot. This is good.

- Optional, allow the tubes to sit at -20°C for at least 15 minutes. This step can go overnight but is normally a good place to break for lunch.
  - ♦ 00:15:00 optional incubation at -20°C
- 16 Centrifuge for 5 minutes at 13,000 rpm.
  - © 00:05:00 spin at 13,000 rpm
- 17 Carefully pour-off the isopropanol. Turn the tube upside down for no more than 2 seconds, as pellets can be slippery, and blot with paper towels.

### Wash

- Add 300μL of 70% ethanol and centrifuge for 5' @ 13,000 rpm.
  - Δ 300 μL 70% EtOH
  - **(5)** 00:05:00 spin at 13,000 rpm

#### Note

There is no need to resuspend the pellet.

The extraction can pause here, just put the tubes at 4°C.

Carefully pour-off ethanol. Turn the tubes upside down and blot as above (speeds drying of EtOH greatly).



20 Allow the plate to sit ~10 minutes at 60°C in to evaporate ethanol.

### Note

Check the tubes to make sure all ethanol has evaporated by visual inspection or wafting before you proceed to the next step. You should not see or smell any ethanol. Pellets are clearly visible.

# Resuspend

21 Resuspend the pellet in 200 µl of 1x TE buffer (or water). Rotate plate upside down gently several times to mix.

#### Note

Optional, put tubes on a shaker at 200rpm for ~30 minutes to resuspend.