

Feb 26, 2019

Neural progenitor expansion



In 1 collection

DOI

dx.doi.org/10.17504/protocols.io.x88frzw

Celeste M M. Karch<sup>1</sup>, Rita Martinez<sup>1</sup>, Jacob Marsh<sup>1</sup>

<sup>1</sup>Washington University in St Louis

Neurodegeneration Method Development Community Tech. support email: ndcn-help@chanzuckerberg.com



Celeste M M. Karch

Washington University in St Louis



Edit and publish protocols, collaborate in communities, share insights through comments, and track progress with run records.

Create free account





DOI: https://dx.doi.org/10.17504/protocols.io.x88frzw

**Protocol Citation:** Celeste M M. Karch, Rita Martinez, Jacob Marsh 2019. Neural progenitor expansion. **protocols.io** <a href="https://dx.doi.org/10.17504/protocols.io.x88frzw">https://dx.doi.org/10.17504/protocols.io.x88frzw</a>





License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working

We use this protocol and it's working

Created: February 17, 2019

Last Modified: February 26, 2019

Protocol Integer ID: 20480

Keywords: neural progenitor expansion

## **Attachments**



## **Guidelines**

This protocol is part of the **IPSC CORTICAL DIFFERENTIATION** collection.

This method should be performed using sterile technique.

## **Materials**

Please refer to the attached full manuscipt for requried materials.

## **Troubleshooting**


# Safety warnings



Please refer to the SDS (Safety Data Sheet) for information about hazards, and to obtain advice on safety precautions.



Using the pre-coated PLO-laminin plate, aspirate laminin from 2-3 wells. Remove supernatant from 15 mL conical tube containing 2 wells of neural rosette clusters. See protocol below.



1.1 On Day 5 of neural aggregate formation, remove media (by pipetting) and carefully wash spheres with  $\frac{100 \, \mu L}{100 \, \mu}$  of pre-warmed DMEM/F12. Repeat 2 times.

#### Note

- 1.2 Remove the last wash and add  $\perp$  50  $\mu$ L of neural induction media to each well.
- 1.3 Aspirate laminin from one well of the pre-coated plate. Using 200  $\mu$ l sterile tips, carefully pipet up spheres from wells using  $\frac{100 \, \mu L}{100 \, \mu}$  volume and transfer thirty-two spheres per well. Repeat above steps for the remaining wells. Incubate cells in  $\frac{100 \, \mu L}{100 \, \mu}$  37 °C, 5% CO<sub>2</sub> and 95% humidified chamber and distribute evenly by making a "T" motion.
- 1.4 After 24:00:00, examine attached aggregates. Remove medium and replace with 2mls/well fresh neural induction medium daily.



#### Note

If some aggregates have not attached, carefully pipet out all medium and replace with 1ml/well fresh neural induction medium. Once 90-100% of aggregates attach, exchange medium daily with 2mls/well neural induction medium.

- 1.5 Monitor spheres daily under microscope for formation of neural rosette structures. Neural rosettes are ready to harvest when spheres have completely flattened and clusters are clearly visible (3-7 days after plating, line dependent).
- 1.6 Harvest neural rosettes by aspirating spent medium. Add and of pre-warmed DMEM/F12 to each well to remove unattached cells (repeat if necessary).
- 1.7 Add 1 mL of Neural Rosette Selection reagent to each well and incubate for up to 01:00:00 at 37 °C (check cells at 00:20:00). Cells are typically collected after 30-45 min incubation. Look for rosette structure to be rounding up without the disturbance of other surrounding cells).
- 1.9 Transfer rosette material from 1 well into a 15 mL conical tube for cryopreservation of neural rosettes and from 2 wells into a separate 15 mL conical tube for neural progenitor expansion. Do not triturate clusters.

#### Note

To maintain a pure culture, it is best to leave some rosettes behind rather than collect all of the rosettes and additional cells.

- 1.10 Centrifuge rosette clusters at 750 rpm for (5) 00:03:00.
  - Add appropriate amount of neural induction media (NIM) to achieve a final volume of 2 mL per well. Pipet clusters up and down breaking them into 1/4 or 1/5 the size of the rosette cluster.



- Examine adherent cells under microscope, aspirate off medium and replace with 2 mL of fresh neural induction medium daily for 3-5 days or until they reach ~80% confluent.
- Make  $\[ \] \Delta \]$  of DMEM/F12 supplemented with 10% FBS by adding  $\[ \] \Delta \]$  of FBS to  $\[ \] \Delta \]$  10 mL of DMEM/F12 to inhibit trypsin activity (termed "Complete Media").
- Remove medium and rinse cells with 1 mL/well of DMEM/F12.
- Harvest cells by adding 1 mL/well of 0.05% trypsin and incubate at 37 °C for 00:03:00.
- Inhibit trypsin activity by adding 4 mL of DMEM/F12 supplemented with 10% FBS to each well.
- 9 Collect cells in 15mL conical tube. Centrifuge at 750 rpm for 00:03:00.

### Note

To minimize bubbles and increase cell yield, add 1mL Complete Media to 15mL conical tube. After trypsinization, add 3mL DMEM/F12 to collect cells and transfer to 15mL conical tube.

Aspirate supernatant and resuspend in 4 12 mL of NIM, pipet at least 3 times to break up large clumps.

#### Note

Small clumps and single cells are acceptable to passage.

- Passage cells to pre-coated PLO-lamin plates (see above) by adding 2 mLs/well of suspended cells for a total of 6 wells.
- 12 Feed with 4 2 mL of fresh NIM daily until they reach 85-95% confluency.



13 **IMPORTANT:** NPCs are best maintained by passaging at a 1:3 dilution. Passaging cells that are more dilute will result in slow growth. Cells will typically become confluent after 2-4 days when plated as a 1:3 dilution. If NPCs are observed to slow in their growth, passage cells and replate without dilution.