



May 11, 2023

## **Organelle isolation from Mouse Embryonic Fibroblasts (MEFs) stably expressing organelle tags for subsequent immunoblotting or proteomic analysis**

DOI

[dx.doi.org/10.17504/protocols.io.ewov1o627lr2/v1](https://dx.doi.org/10.17504/protocols.io.ewov1o627lr2/v1)

Matthew Taylor<sup>1</sup>, Pui Yiu Lam<sup>1</sup>, Francesca Tonelli<sup>1</sup>, Dario R Alessi<sup>1</sup>

<sup>1</sup>Medical Research Council Protein Phosphorylation and Ubiquitylation Unit, School of Life Sciences, University of Dundee, Dow Street, Dundee DD1 5EH, UK



**Francesca Tonelli**

MRC-PPU at The University of Dundee

### Create & collaborate more with a free account

Edit and publish protocols, collaborate in communities, share insights through comments, and track progress with run records.

Create free account

OPEN  ACCESS



**DOI:** <https://dx.doi.org/10.17504/protocols.io.ewov1o627lr2/v1>

**Protocol Citation:** Matthew Taylor, Pui Yiu Lam, Francesca Tonelli, Dario R Alessi 2023. Organelle isolation from Mouse Embryonic Fibroblasts (MEFs) stably expressing organelle tags for subsequent immunoblotting or proteomic analysis.

**protocols.io** <https://dx.doi.org/10.17504/protocols.io.ewov1o627lr2/v1>

**License:** This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

**Protocol status:** Working

**We use this protocol and it's working**

**Created:** April 21, 2023

**Last Modified:** May 31, 2024

**Protocol Integer ID:** 80869

**Keywords:** Organelle isolation from cells, ASAPCRN, organelle isolation from mouse embryonic fibroblast, organelle tags for subsequent immunoblotting, rapid isolation of intact organelle, organelle isolation, organelle tag, tagged lysosome, expressing organelle tag, mouse embryonic fibroblast, including lysosome, intact organelle, organelle, mass spectrometry proteomic analysis, proteomic analysis, cultured cell, immunoblotting analysis, cell, immunopurification of ha, cell homogenate, immunopurification

**Funders Acknowledgements:**

**Aligning Science Across Parkinson's**

**Grant ID:** ASAP-000463

## Disclaimer

DISCLAIMER – FOR INFORMATIONAL PURPOSES ONLY; USE AT YOUR OWN RISK

The protocol content here is for informational purposes only and does not constitute legal, medical, clinical, or safety advice, or otherwise; content added to [protocols.io](#) is not peer reviewed and may not have undergone a formal approval of any kind. Information presented in this protocol should not substitute for independent professional judgment, advice, diagnosis, or treatment. Any action you take or refrain from taking using or relying upon the information presented here is strictly at your own risk. You agree that neither the Company nor any of the authors, contributors, administrators, or anyone else associated with [protocols.io](#), can be held responsible for your use of the information contained in or linked to this protocol or any of our Sites/Apps and Services.

## Abstract

We describe here a method to perform rapid isolation of intact organelles (including lysosomes and Golgi) from mouse embryonic fibroblasts stably expressing an organelle tag (TMEM192-3xHA, or LysoTag, and TMEM115-3xHA, or GolgiTag). First, cells are broken using a ball-bearing cell breaker, leading to plasma membrane rupture, while lysosomes and Golgi remain intact. Then, the cell homogenate is incubated with anti-HA magnetic beads to allow for immunopurification of HA-tagged lysosomes or Golgi in less than 15 minutes. The organelles purified using this method are highly enriched, intact, contaminant-free and, depending on solubilisation buffer, can be used for various downstream applications, including immunoblotting analysis and mass spectrometry proteomic analysis (as described here), but also metabolomic or lipidomic analysis. This protocol can be adapted to isolate organelles from commonly cultured cells, such as HEK293 and A549 cells, that express an organelle tag.



## Attachments



[meh7bhc4x.docx](#)

46KB

## Guidelines

Protocol overview:

1. Organelle isolation from cells expressing organelle tags.
2. Analysis of isolated organelles by immunoblotting
3. Analysis of isolated organelles by mass spectrometry (proteomic analysis)

*For the generation of MEFs stably expressing organelle tags, see*  
***[dx.doi.org/10.17504/protocols.io.6qpvr456bgmk/v1](https://dx.doi.org/10.17504/protocols.io.6qpvr456bgmk/v1)***

## Materials

### Reagents

- MEFs stably expressing organelle tag: GolgiTag (Tmem115-3xHA) or LysoTag (Tmem192-3xHA), or control empty tag (3xHA).

#### Note

For the generation of MEFs stably expressing organelle tags, see [dx.doi.org/10.17504/protocols.io.6qpvr456bgmk/v1](https://doi.org/10.17504/protocols.io.6qpvr456bgmk/v1)

- DPBS no calcium no magnesium **Gibco - Thermo Fisher Scientific Catalog #14190169**

#### ■ KPBS Buffer:

	A	B
	KCL	136 mM
	KH <sub>2</sub> PO <sub>4</sub> in MS grade water	10 mM

Adjust to pH 7.25 with KOH.

- "Supplemented KPBS" (to be prepared immediately before harvesting the cells): KPBS buffer supplemented with 1X phosSTOP phosphatase inhibitor cocktail (PhosSTOP tablet: Roche, REF# 04906837001) and 1X protease inhibitor cocktail (cOmplete EDTA-free protease inhibitor cocktail tablet: Roche, REF# 11873580001)
- Thermo Scientific™ Pierce™ Anti-HA Magnetic Beads (Thermo Fisher Scientific, cat # 13474229)

#### ■ Lysis Buffer for Immunoblotting analysis:

	A	B
	Tris-HCl, pH 7.5	50 mM
	Triton X-100	1% (by volume)
	glycerol	10% (by volume)
	NaCl	150 mM
	sodium orthovanadate	1 mM
	sodium fluoride	50 mM










A	B
sodium $\beta$ -glycerophosphate	10 mM
sodium pyrophosphate	5 mM
microcystin-LR	0.1 $\mu$ g/ml
cOmplete Mini (EDTA-free) protease inhibitor (Roche)	1 tablet






▪ **Lysis Buffer for Mass spectrometry analysis:**

A	B
SDS	2% v/v
HEPES pH 8	20 mM
phosSTOP phosphatase inhibitor cocktail (Roche)	1X
protease inhibitor cocktail (completeEDTA-free, Roche)	1X

▪ **STrap washing buffer:**

A	B
MeOH	90 %
TEABC at pH 7.2	10 %

- LC-MS grade H<sub>2</sub>O (  LC-grade Water **Fisher Scientific Catalog #10777404** )
-  Triethylammonium bicarbonate buffer **Merck MilliporeSigma (Sigma-Aldrich) Catalog #18597** – Make a [M] 50 millimolar (mM) and [M] 300 millimolar (mM) stock in LC-MS grade H<sub>2</sub>O,  8
-  Pierce&trade; TCEP-HCl **Thermo Fisher Catalog #20491** –Make a [M] 100 millimolar (mM) stock in [M] 300 millimolar (mM) TEABC
-  Iodoacetamide **Merck MilliporeSigma (Sigma-Aldrich) Catalog #11149** – Make a [M] 200 millimolar (mM) stock in [M] 300 millimolar (mM) TEABC
-  Trypsin/Lys-C Mix, Mass Spec Grade, 5 × 20ug **Promega Catalog #V5073** ) –  20  $\mu$ g of trypsin/Lys-C reconstitute in  800  $\mu$ L of [M] 50 millimolar (mM) TEABC at a final concentration of  25  $\mu$ g/mL

-  SDS Micro-Pellets **Formedium Catalog #SDS0500** – make a 20% solution in MilliQ water
-  Phosphoric acid **Merck MilliporeSigma (Sigma-Aldrich) Catalog #345245** – Make a 12.5% solution in MilliQ water
-  Methanol LC-MS grade B&J Brand **VWR International (Avantor) Catalog #BJLC230-2.5**
-  Acetonitrile LC-MS grade B&J Brand **VWR International (Avantor) Catalog #BJLC015-2.5**
- Formic acid (Sigma; Cat # 56302)
-  Trifluoroacetic acid **Merck MilliporeSigma (Sigma-Aldrich) Catalog #T6508**

## Equipment

### Equipment

**BELLY DANCER ORBITAL SHAKER**

NAME

ORBITAL SHAKER

TYPE

IBI

BRAND

BDRAA115S

SKU

<https://www.ibisci.com/products/belly-dancer-shaker><sup>LINK</sup>

### Equipment

**DynaMag-2**

NAME

Magnet

TYPE

Invitrogen

BRAND

12321D

SKU

<https://www.thermofisher.com/order/catalog/product/12321D#/12321D><sup>LINK</sup>



- Isobiotec Cell-Breaker (isobiotec Vertriebs UG)

## Equipment

**Micro Star 17 / 17R, Microcentrifuges, Ventilated/Refrigerated**

NAME

Microcentrifuge

TYPE

VWR®

BRAND








521-1647

SKU

<https://in.vwr.com/store/product/8306728/microcentrifuges-ventilated-refrigerated-micro-star-17-17r><sup>LINK</sup>

- Bioruptor (Diagenode)
- Thermomixer (Eppendorf, UK)
- SpeedVac Vacuum Concentrator
- UltiMate 3000 RSLC nano-HPLC system (Thermo Fisher Scientific, UK) coupled to an Orbitrap Exploris™ 480 mass spectrometer (Thermo Fisher Scientific, UK)
- Precolumn: Acclaim PepMap™ 100, C18, 100 µm x 2 cm, 5 µm, 100 Å
- Analytical column: PepMap™ RSLC C18, 75 µm x 50 cm, 2 µm, 100 Å

## Consumables

-  Corning® cell lifter **Merck MilliporeSigma (Sigma-Aldrich) Catalog #CLS3008-100EA**
-  SafeSeal reaction tube 1.5 ml PP PCR Performance Tested Low protein-binding **Sarstedt Catalog #72.706.600**
-  Greiner Bio-One™ Polypropylene Pipette Tip **Fisher Scientific Catalog #686271** and  PIPETTE TIP 10 - 100 µL SUITABLE FOR EPPENDORF 96 PIECES / ST RACK **greiner bio-one Catalog #685261**
- Stripetter/stripette gun and stripettes
- Set of Gilson pipettes P10, P200, P1000
-  Terumo® Syringe 3-part Syringe **Terumo Catalog #MDSS01SE**
-  Becton Dickinson Disposable needles 21G x 1 1/2 inch **Becton Dickinson (BD) Catalog #304432**
-  Syringe PP/PE without needle **Merck MilliporeSigma (Sigma-Aldrich) Catalog #Z116866**



-  S-Trap™ micro columns ( $\leq 100\ \mu\text{g}$ ) **Protifi Catalog #C02-micro**

## Troubleshooting






## Isobiotec cell-breaker assembly

- 1 Insert the metal ball of choice inside the cell breaker.

### Note

**Note:** For MEFs, we recommend a 12  $\mu\text{m}$  clearance.

- 2 Screw the lids on tightly.

- 3 Push  3 mL of KPBS through the cell breaker to wash it.



- 4 Carefully tap dry.

- 5 Place the cell-breaker on aluminium foil  On ice until use (Step 28).


- 6 **To clean the Isobiotec cell-breaker between samples and at the end of the experiment:**

- 6.1 Open the cell-breaker from one side.


- 6.2 Take the metal ball out and rinse with MilliQ water.


- 6.3 Flush the cell breaker thoroughly with MilliQ water using 5-mL syringes through both syringe inlets whilst covering the opening on the side of the cell breaker.

- 6.4 Reassemble the cell-breaker by re-inserting the metal ball into the instrument and close the side panel tightly using the screws.

- 6.5 Flush the cell breaker through both syringe inlets with  5 mL of KPBS using 5-ml syringes.

**Note**



**Note:** There will be some residual KPBS left in the cell-breaker (approximately  200  $\mu\text{L}$ ), this is optimal.

- 6.6 Proceed to homogenise the next sample.
- 6.7 Once finished, flush the cell breaker thoroughly with MilliQ water using 5-mL syringes through both syringe inlets whilst covering the opening on the side of the cell breaker.
- 6.8 Take all pieces apart (both side panels, panel screws and the metal ball).
- 6.9 Clean each part with a generous amount of 70% (v/v) ethanol in MilliQ water.
- 6.10 Wipe all parts dry and leave pieces apart to air-dry  Overnight .

**Note**






**Note:** *Packing up the cell-breaker before it is dry will lead to development of rust and colouring of the metal parts.*

## Anti-HA Magnetic beads preparation

- 7 Transfer n x  100  $\mu\text{L}$  of anti-HA Magnetic Beads (where n = number of samples) into a low binding Eppendorf tube.
- 8 Immobilize the beads by placing the tube into a Dyna-Mag tube holder for  00:00:30 .
- 9 Remove the supernatant using a pipette.

30s



- 10 Gently resuspend the beads in  1 mL of KPBS.
- 11 Repeat steps 8 to 10.
- 12 Immobilize the beads by placing the tube into a Dyna-Mag tube holder for  00:00:30 .
- 13 Remove the supernatant using a pipette.
- 14 Gently resuspend the beads from step 13 in n x  100  $\mu$ L of KPBS (where n = number of samples you have) to make a 1:1 slurry.
- 15 Aliquot the washed beads from step 14 into fresh low-binding Eppendorf tubes (  100  $\mu$ L of slurry for each sample).
- 16 Leave the tubes  On ice until use (step 34).



30s

## Organelle isolation from cells expressing organelle tags

- 17 For each experimental condition, seed cells into one 15 cm dish.










### Note

**Note:** *In parallel, seed cells transduced to express HA-empty as a control.*

- 18 When cells have reached a confluency of ~ 90%, aspirate the culture medium.
- 19 Quickly wash once by adding  5 mL of PBS at  Room temperature .
- 20 Completely aspirate the PBS.






- 21 Add  1 mL of ice-cold supplemented KPBS. 
- 22 Place the cell dishes  On ice .
- 23 Scrape the cells on the dish using a cell lifter to ensure all cells are detached from the dish.
- 24 Using a pipette, transfer the cell suspension to a low binding Eppendorf  On ice .
- 25 Spin down at  1000 x g, 4°C, 00:02:00 . 
- 26 Discard the supernatant.
- 27 Resuspend the pellet in  1 mL of ice-cold supplemented KPBS.
- 28 Using a 1-ml syringe and 21G needle, transfer the cell suspension from step 27 into a KPBS rinsed, ice-cold Isobiotec cell-breaker (with gap-size of  12  $\mu\text{m}$  ) kept  On ice (Step 5).
- 29 Homogenise the cells with 10 passes through the cell breaker using 2  $\times$  1-ml syringes.
- Note**
- Note:**
- One pass is defined by the cell suspension passing through both syringes.
  - The homogenisation requires more force with more passes. Pay extra care to make sure the syringes are securely in their seals and that the sample doesn't leak out. If you encounter too much pressure for passing the homogenate through the cell-breaker, consider using a ball that leaves a larger clearance gap.
- 30 Collect the homogenate from the cell breaker into a fresh Eppendorf tube using a 1-ml syringe.

**Note**



**Note:** To extract as much sample as possible from the cell-breaker post-homogenisation, push air into the cell-breaker using a syringe and collect from the other seal using another syringe.

31 Transfer the resulting homogenate to a low binding Eppendorf  On ice .

32 Preclear the homogenate by centrifugation at  1000 x g, 4°C, 00:02:00 .

2m





33 For each sample, transfer  100 µL to a new low binding Eppendorf (= input)  
 On ice .

34 Add the remaining homogenate to  100 µL of the pre-washed HA-Magnetic beads (Step 16).



35 Mix gently by flicking the bottom of the tube.





36 Incubate with agitation on a Belly Dancer orbital shaker for  00:05:00 at  4 °C .


5m



37  30s


**Note**

The following steps should ideally be performed in a  4 °C cold room. If not available, then keep working  On ice .

Place the tubes from Step 36 on a magnetic tube holder for  00:00:30 to immobilise the beads.

38 Discard the supernatant or collect as a flow-through sample.





39 Resuspend the beads from Step 38 in  1 mL of supplemented KBPS.


40 Immobilise the beads by placing the tubes in a Dyna-Mag tube holder for  00:00:30 .

30s

41 Discard the supernatant.

42 Repeat steps 39 to 41 twice.

43 Resuspend the beads in  1 mL of supplemented KPBS and transfer to a new low binding Eppendorf tube  On ice .

44 Place the tubes in a Dyna-Mag tube holder for  00:00:30 .

30s



45 Discard the supernatant.

46 The organelle IP beads (from step 45) and the input (from step 33) can now be processed for either 1) immunoblotting analysis, or 2) mass spectrometry analysis, as detailed below..

## Sample analysis by immunoblotting


47 **Input** (from step 33)

47.1 Dilute in Lysis Buffer compatible for Immunoblotting analysis to a 1:1 ratio.

47.2 Incubate  On ice for  00:10:00 .

10m




47.3 Clarify by centrifugation at  17000 x g, 4°C, 00:10:00 .



10m



47.4 Transfer the supernatant to a new low binding tube.


48 **Organelle IP beads** (from step 45).

48.1 Resuspend in  100  $\mu$ L of lysis buffer compatible for immunoblot analysis.

48.2 Incubate  On ice for  00:10:00 .

10m




48.3 Immobilise the beads by placing the tubes in a Dyna-Mag tube holder for  00:00:30 .

30s

48.4 Transfer the supernatant to a new low binding tube.



49 Quantify protein concentration by BCA assay.

50 Samples can be analysed by quantitative immunoblotting analysis as described in **[dx.doi.org/10.17504/protocols.io.bsgrnbv6](https://dx.doi.org/10.17504/protocols.io.bsgrnbv6)**, ensuring an equal protein amount of both the input and IP is loaded (~  2  $\mu$ g ).



## Sample analysis by Mass Spectrometry: Sample Processing

51 **Input** (from step 33):

51.1 Dilute in lysis buffer compatible for mass spectrometry analysis to a 1:1 ratio.

51.2 Sonicate using a Bioruptor (  00:00:30 ON,  00:00:30 OFF for 15 cycles).

1m

51.3 Clarify by centrifugation at  17000 x g, 4°C,  00:10:00 .



10m



51.4 Transfer the supernatant to a clean low binding tube.



52 **Organelle IP beads** (from step 45):

52.1 Resuspend in  100  $\mu$ L of lysis buffer compatible for mass spectrometry analysis.


52.2 Incubate at  Room temperature for  00:10:00 .

10m





52.3 Sonicate using a Bioruptor (  00:00:30 ON,  00:00:30 OFF for 15 cycles).

1m

52.4 Immobilise the beads by placing the tubes in a Dyna-Mag tube holder for  00:00:30 .



30s

52.5 Transfer the supernatant to a new low binding tube.

53 **Reduction:** Add TCEP to the samples from step 51.4 and 52.5 to a final concentration of  5 millimolar (mM) and place on a thermomixer at  1100 rpm, 60°C, 00:30:00 .




54 Cool the samples down to  Room temperature .

55 **Alkylation:** Add IAA to the samples from step 54 to a final concentration of  20 millimolar (mM) and place on a thermomixer at  1100 rpm, 25°C, 00:30:00 , shielded from light.



56 Add sodium dodecyl sulfate (SDS) to a final concentration of 5% (v/v) and phosphoric acid to a final concentration of 1.2% (v/v) to the samples from step 55.

57 Dilute the sample with an additional volume of wash buffer (wash buffer volume equals to 6-fold of the sample volume) (90% MeOH, 10% TEABC at  7.2 ) and mix by







vortexing.



58 Load each sample onto a S-Trap™ column.

59 Centrifuge at  1000 x g, 00:01:00 .

1m










60 Discard the flow-through.

61 Wash the S-Trap™ columns three times with  150 µL wash buffer (90% MeOH, 10% TEABC at  7.2 ). Discard the flowthrough after each wash.





62 Transfer the S-Trap column to a fresh 1.5-mL low binding tube.

63 Prepare a Trypsin/Lys-C Mix in  50 millimolar (mM) TEABC solution,  8 to a  25 µg/mL concentration.

64 On-column digestion: Add  60 µL (  1.5 µg ) Trypsin/Lys-C Mix from step 63 to each S-Trap column from step 61 and incubate on a thermomixer at  47 °C for  01:00:00 with no agitation.




1h




65 Reduce the temperature on the thermomixer to  22 °C and incubate  Overnight with no agitation.

1h




66 **Peptide elution:** Add  60 µL of  50 millimolar (mM) TEABC solution, pH  8 to each S-Trap column and centrifuge.








67 Add  60 µL of 0.15% (v/v) formic acid (FA) aqueous solution to each S-Trap column and centrifuge.



68 Add  60 µL of elution buffer (80% ACN with 0.15% FA in aqueous solution) to each S-Trap column and centrifuge.






- 69 Repeat step 68.
- 70 Discard the S-Trap columns.
- 71 Snap-freeze the samples on dry ice.
- 72 Dry the samples at  35 °C using a SpeedVac Vacuum Concentrator.
- 73 Resuspend the samples from step 72 in  60 µL solution containing 3% (v/v) ACN and 0.1% (v/v) FA in LC-MS grade H<sub>2</sub>O.
- 74 Incubate the samples on a thermomixer at  1200 rpm, 22°C, 00:30:00 . 
- 75 Sonicate the samples for  00:30:00 in a water bath. 30m
- 76 Estimate peptide concentration of each sample using a NanoDrop instrument by measuring the solution absorbance A<sub>280</sub> at 224 nm wavelength.

## Sample analysis by Mass Spectrometry: Sample Injection onto Mass Spectrometer

77

### Note

***Note: Liquid chromatography tandem mass spectrometry (LC-MS/MS) is performed using an UltiMate 3000 RSLC nano-HPLC system coupled to an Orbitrap Exploris<sup>TM</sup> 480 mass spectrometer.***

For each sample, load  4 µg of digested protein sample onto the nano-HPLC system individually.



- 78 Trap the peptides using a precolumn (Acclaim PepMap<sup>TM</sup> 100, C18, 100  $\mu\text{m}$  x 2 cm, 5  $\mu\text{m}$ , 100  $\text{\AA}$ ) using an aqueous solution containing 0.1% (v/v) TFA.
- 79 Separate the peptides using an analytical column (PepMap<sup>TM</sup> RSLC C18, 75  $\mu\text{m}$  x 50 cm, 2  $\mu\text{m}$ , 100  $\text{\AA}$ ) at 45  $^{\circ}\text{C}$  using
- a linear gradient of 8 to 25% solvent B (an 80% ACN and 0.1% FA solution) for 01:38:00 ,
  - 25 to 37% solvent B for 00:15:00 ,
  - 37 to 95% solvent B for 00:02:00 ,
  - 95% solvent B for 00:08:30 ,
  - 95% to 3% solvent B for 00:00:30 , and
  - 3% solvent B for 00:09:30 .
- Set the flow rate at 250 nL/min.
- 80 Acquire data in data-independent acquisition (DIA) mode containing 45 isolated m/z windows ranging from 350 to 1500.
- 81 Use a higher-energy collisional dissociation (HCD) with nitrogen for peptide fragmentation with the following isolation window:

2h 13m  
30s

	A	B	C
	<b>m/z</b>	<b>z</b>	<b>Isolation Window</b>
	383.4	3	66.8
	423.0	3	13.5
	435.0	3	11.5
	446.5	3	12.5
	458.0	3	11.5
	469.0	3	11.5
	480.0	3	11.5



	A	B	C
	490.5	3	10.5
	501.0	3	11.5
	512.0	3	11.5
	523.0	3	11.5
	533.5	3	10.5
	544.0	3	11.5
	554.5	3	10.5
	565.0	3	11.5
	575.5	3	10.5
	586.0	3	11.5
	597.5	3	12.5
	609.5	3	12.5
	621.5	3	12.5
	633.0	3	11.5
	645.0	3	13.5
	657.5	3	12.5
	670.5	3	14.5
	684.0	3	13.5
	697.0	3	13.5



	A	B	C
	710.5	3	14.5
	725.5	3	16.5
	741.0	3	15.5
	756.5	3	16.5
	773.5	3	18.5
	791.0	3	17.5
	808.5	3	18.5
	827.0	3	19.5
	846.5	3	20.5
	866.5	3	20.5
	887.5	3	22.5
	910.5	3	24.5
	935.5	3	26.5
	962.5	3	28.5
	992.0	3	31.5
	1025.0	3	35.5
	1063.0	3	41.5
	1108.5	3	50.5
	1391.6	3	516.8

## Sample analysis by Mass Spectrometry: Data analysis

- 82 The DIA MS experiment's raw data were analysed using the DIA-NN software (Reference 1), employing a library-free search mode based on a reviewed Swiss-Prot database downloaded from UniProt.
- 83 Trypsin/P was selected as the digestive enzyme, and up to 2 missed cleavages were allowed. Carbamidomethylation at Cysteine residue was set as a fixed modification, while oxidation at methionine residue was included as a variable modification. The software automatically detected and adjusted the mass error (ppm).
- 84 A protein identification cut-off of 1% FDR was used, and a protein quantification required a minimum of 2 peptides in at least 75% samples.
- 85 The protein group search results generated from DIA-NN software were then imported into Perseus software (Reference 2) for statistical analysis.
- 86 For the organelle-IP samples, IP samples were first compared against the relevant mock IP samples to classify proteins significantly enriched, using a fold-change > 1.5 and p-value < 0.05.
- 87 The organelle enriched proteins were then compared against genotypes or treatments to investigate protein level changes at the targeted organelle.
- 88 For the whole cell lysate samples, proteins were directly compared against genotypes or treatments to determine the proteome changes in the cells.
- 89 Significant up-/down-regulated proteins (fold-change > |1.5| and p-value < 0.05) obtained from organelle-IP and whole cell lysate samples were then submitted to metascape (reference 3) for enrichment analysis.
- 90 The clustering analysis using metascape focuses on enrichment of GO biological processes pathway, GO molecular functions, and GO cellular components with p-value < 0.01.
- 91 The text files generated from Perseus software were imported into an in-house software, Curtain 2.0, for data visualisation.



## Protocol references

### References

1. Demichev, V.; Messner, C. B.; Vernardis, S. I.; Lilley, K. S.; Ralser, M., DIA-NN: neural networks and interference correction enable deep proteome coverage in high throughput. *Nat Methods* **2020**, *17* (1), 41-44.
2. Tyanova, S.; Temu, T.; Sinitcyn, P.; Carlson, A.; Hein, M. Y.; Geiger, T.; Mann, M.; Cox, J., The Perseus computational platform for comprehensive analysis of (prote)omics data. *Nature Methods* **2016**, *13* (9), 731-740.
3. Zhou, Y.; Zhou, B.; Pache, L.; Chang, M.; Khodabakhshi, A. H.; Tanaseichuk, O.; Benner, C.; Chanda, S. K., Metascape provides a biologist-oriented resource for the analysis of systems-level datasets. *Nat Commun* **2019**, *10* (1), 1523.
4. [dx.doi.org/10.17504/protocols.io.6qpvr456bgmk/v1](https://doi.org/10.17504/protocols.io.6qpvr456bgmk/v1)
5. [dx.doi.org/10.17504/protocols.io.bsgrnbv6](https://doi.org/10.17504/protocols.io.bsgrnbv6)