


Aug 10, 2020 Version 7

plasma preparation_exRNAQC V.7

DOI

dx.doi.org/10.17504/protocols.io.n99dh96



Anneleen Decock¹

¹Center for Medical Genetics Ghent (CMGG), Cancer Research Institute Ghent (CRIG)

CMGG



Anneleen Decock

Center for Medical Genetics Ghent (CMGG), Cancer Research In...

OPEN  ACCESS



DOI: dx.doi.org/10.17504/protocols.io.n99dh96

Protocol Citation: Anneleen Decock 2020. plasma preparation_exRNAQC. **protocols.io**
<https://dx.doi.org/10.17504/protocols.io.n99dh96>

License: This is an open access protocol distributed under the terms of the **Creative Commons Attribution License**, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working

We use this protocol and it's working

Created: April 06, 2018

Last Modified: August 10, 2020

Protocol Integer ID: 11297

Keywords: plasma

Disclaimer

DISCLAIMER – FOR INFORMATIONAL PURPOSES ONLY; USE AT YOUR OWN RISK

The protocol content here is for informational purposes only and does not constitute legal, medical, clinical, or safety advice, or otherwise; content added to [protocols.io](https://www.protocols.io) is not peer reviewed and may not have undergone a formal approval of any kind. Information presented in this protocol should not substitute for independent professional judgment, advice, diagnosis, or treatment. Any action you take or refrain from taking using or relying upon the information presented here is strictly at your own risk. You agree that neither the Company nor any of the authors, contributors, administrators, or anyone else associated with [protocols.io](https://www.protocols.io), can be held responsible for your use of the information contained in or linked to this protocol or any of our Sites/Apps and Services.

Abstract

This protocol describes how to prepare plasma from venous blood draw.

Attachments



[plasma preparation.p...](#)

60KB

Guidelines

- In the Center for Medical Genetics Gent (CMGG), plasma preparation is performed in the blood lab. Guidelines on how to handle blood samples and how to work in this lab are described in H5.3-OP2-B1.
- Take pictures (optional) on a white background, upright position

Materials


MATERIALS

 Liquid Nitrogen


 Pipettes


 Safe-Lock cup DNA LoBind 1,5ml PCR clean **Eppendorf Catalog #A08970**

 Cryotube **Thermo Fisher Scientific Catalog #10674511**


 Centrifuge with swinging bucket rotor (centrifugation speed up to 2500 g (rcf)) and buckets for blood collection tubes and conical 15 ml tubes

 Disposable lab coat

 Nitrile powder-free gloves

 Nalgene® 62080-00 VERSI-DRY® Lab Soaker Bench Protector Mat, White Standard Absorbency **Thermo Fisher Scientific Catalog #NAL-62080-00**

 Filter tips

 Racks for the different types of tubes

 Conical tube, 15 ml **greiner bio-one Catalog #188271**



Centrifugation step 1: 20 min at 400 g (rcf)

- 1
 - Invert tubes 5 times before centrifugation
 - Spin tubes for 20 min at 400 g (rcf) (without brake), at room temperature. Note time point of start of centrifugation
 - Pipette platelet-rich plasma (PRP) carefully into a new collection tube, leave \pm 0.5 cm above the buffy coat (do not disturb the buffy coat)
 - Invert the PRP tube before aliquoting. Aliquot the PRP into cryovials or LoBind tubes, snap freeze in liquid nitrogen and store at -80°C (note time point of snap freeze), and/or continue to prepare platelet-poor plasma (PPP)

Centrifugation step 2: 10 min at 800 g (rcf)

- 2
 - Spin the PRP for 10 min at 800 g (rcf) (without brake) to obtain platelet-poor plasma (PPP), at room temperature
 - Pipette PPP carefully into a new collection tube, leave \pm 0.5 cm above pellet (do not disturb pellet)
 - *Optional: If platelets need to be collected, resuspend pellet in remaining volume above pellet, transfer to 1.5 ml tube, and spin again for 10 min at 800 g (rcf) (without brake), remove volume and snap freeze pellet in 1.5 ml tube. Note time point of snap freeze*
 - Invert the PPP tube before aliquoting. Aliquot the PPP into cryovials or LoBind tubes, snap freeze in liquid nitrogen and store at -80°C (note time point of snap freeze), and/or continue to prepare platelet-free plasma (PFP)

Centrifugation step 3: 15 min at 2500 g (rcf)

- 3
 - Spin the PPP for 15 min at 2500 g (rcf) (without brake) to obtain platelet-free plasma (PFP), at room temperature
 - Pipette PFP carefully into a new collection tube, leave \pm 0.5 cm above pellet (do not disturb pellet)
 - Aliquot the PFP into cryovials or LoBind tubes, snap freeze in liquid nitrogen and store at -80°C (note time point of snap freeze)