

Jun 03, 2019

Version 1

# **③** Prepare NGM plates with fungzizone V.1

DOI

dx.doi.org/10.17504/protocols.io.3npgmdn

Research Cancer UK / Wellcome Gurdon Institute media kitchen<sup>1</sup>

<sup>1</sup>Research Cancer UK / Wellcome Gurdon Institute



#### **Cristian Riccio**

University of Cambridge

### Create & collaborate more with a free account

Edit and publish protocols, collaborate in communities, share insights through comments, and track progress with run records.

Create free account

OPEN ACCESS



DOI: https://dx.doi.org/10.17504/protocols.io.3npgmdn

**Protocol Citation:** Research Cancer UK / Wellcome Gurdon Institute media kitchen 2019. Prepare NGM plates with fungzizone. **protocols.io** <a href="https://dx.doi.org/10.17504/protocols.io.3npgmdn">https://dx.doi.org/10.17504/protocols.io.3npgmdn</a>

**License:** This is an open access protocol distributed under the terms of the **Creative Commons Attribution License**, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working

We use this protocol and it's working

Created: June 03, 2019



Last Modified: June 03, 2019

Protocol Integer ID: 23983

Keywords: ngm plates with fungzizone prepare ngm plate, fungzizone prepare ngm plate, ngm plate, fungizon, ngm

### Abstract

Prepare NGM plates with fungizon

#### **Materials**

#### **MATERIALS**

- Petri Dish P212121 Catalog #LI-PD01100
- X Calcium Chloride
- Magnesium Sulfate Heptahydrate Certified AR for Analysis Fisher Chemical Fisher Scientific Catalog #M/1050/53
- Potassium Dihydrogen Orthophosphate Certified AR for Analysis Fisher Chemical Fisher Scientific Catalog # P/4800/53
- X NGM medium
- **X** cholesterol
- **X** fungizone

### **Troubleshooting**

## Safety warnings



Make sure you know how to use the autoclave before starting this protocol.



1 NGM+Fungizone\_plates(1L).xls

2

Ingredie nts			Quantity
NGM Media			1L
Cholest erol 5mg/ml		1ml	
1M CaCl2			1ml
1M MgSO4			1ml
1M KH2PO4			25ml
Petri dish	30mm		as required
	50mm		as required
	90mm		as required
Fungizo ne	400 microlitres		1 microtub be

3

First thing in the morning, melt 1L NGM in autoclave
Once melted, place in water bath set at 58oC, leave until cooled (-at least 2hours) normally left until the afternoon.
Set out the plates on bench before starting pouring process.



Put melted NGM media on stirrer
Using 1ml gilson add the Cholesterol,replace the lid and return to the bench to give a good stir to dispense all the cholesterol.
Add the KH2PO4 using sterile 50ml syringe and 0.22µm filter.
Stir for a few seconds until well mixed. Add Fungizone ensuring all is added to the NGM.
Dispense media using a peristaltic pump. Add 4.20ml in 30mm plates, 9.00ml in 50mm plates, 4.50ml in 6 well plates and 2.5ml in 12 well plates. When set stack upside down in plastic trays.