

Jul 26, 2019 Version 3

Preparing 10 L of M9 buffer for nematode culture V.3

DOI

dx.doi.org/10.17504/protocols.io.5wjg7cn

Gurdon Institute media kitchen¹

¹Cancer Research UK / Wellcome Gurdon Institute



Cristian Riccio

University of Cambridge

OPEN  ACCESS



DOI: dx.doi.org/10.17504/protocols.io.5wjg7cn

Protocol Citation: Gurdon Institute media kitchen 2019. Preparing 10 L of M9 buffer for nematode culture. [protocols.io](#)
<https://dx.doi.org/10.17504/protocols.io.5wjg7cn>

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working

We use this protocol and it's working

Created: July 26, 2019

Last Modified: July 26, 2019

Protocol Integer ID: 26283

Keywords: M9, m9, nematodes, worms

Abstract

Prepare 10 litres of M9 solution for collecting and washing *C. elegans*.

Materials

MATERIALS

 double distilled water (ddH₂O)

 Di-Sodium Hydrogen Orthophosphate Dihydrate Certified AR for Analysis Fisher
Chemical Catalog #S/4450/53

 Sodium chloride meets analytical specification of Ph.Eur Fisher Chemical Fisher
Scientific Catalog #S/3160/65

 Magnesium Sulfate Heptahydrate Certified AR for Analysis Fisher Chemical Fisher
Scientific Catalog #M/1050/53

 Potassium Dihydrogen Orthophosphate Certified AR for Analysis Fisher Chemical Fisher
Scientific Catalog # P/4800/53

 SYCHEMA autoclave Syschem

Safety warnings

-  This protocol makes use of an autoclave. Make sure you know how to use it properly before starting the protocol.

1

20m

Ingredients	Quantity	
Na ₂ HPO ₄	60g	
KH ₂ PO ₄	30g	
NaCl	50g	
Double distilled H ₂ O	up to 10L	
Add 1M MgSO ₄ after autoclaving @ 100ul/100ml		

 M9_buffer_10L.xls

2

15m

1	Dissolve ingredients in 8L double distilled H ₂ O
2	Adjust volume to 10L using double distilled H ₂ O
3	Measure or use pump to dispense aliquots accurately.
4	Label, date and autoclave.
5	After autoclaving, add 100ul 1M MgSO ₄ per 100ml. (ie. 100ul to 100ml and 200ul to 200ml bottles).
NB	1M MgSO ₄ at 1ul/1ml in the M9 buffer gives a final concentration of 1mM

3 The autoclave is SYCHEMA VS Series. The media cycle is 15 minutes at 121 degrees centigrade. It is then cooled down in the machine for 3 hours.

3h 15m

4 After autoclaving, add 100 μ l 1M MgSO₄ per 100 ml. (ie. 100 μ l to 100 ml and 200 μ l to 200 ml bottles).

10m

NB: 1M MgSO₄ at 1 μ l/1ml in the M9 buffer gives a final concentration of 1 mM