

Jun 13, 2019

Transient transcriptome sequencing: experimental protocol to monitor genome-wide RNA synthesis including enhancer transcription

DOI


dx.doi.org/10.17504/protocols.io.3vzgn76

Saskia Gressel¹, Katja Lidschreiber¹, Patrick Cramer¹

¹Max-Planck-Institute for Biophysical Chemistry, Department of Molecular Biology, Am Faßberg 11, 37077 Göttingen, Germany



Saskia Gressel



Create & collaborate more with a free account

Edit and publish protocols, collaborate in communities, share insights through comments, and track progress with run records.

Create free account

OPEN  ACCESS



DOI: <https://dx.doi.org/10.17504/protocols.io.3vzgn76>

Protocol Citation: Saskia Gressel, Katja Lidschreiber, Patrick Cramer 2019. Transient transcriptome sequencing: experimental protocol to monitor genome-wide RNA synthesis including enhancer transcription. **protocols.io**

<https://dx.doi.org/10.17504/protocols.io.3vzgn76>

Manuscript citation:

This manuscript will be published as a chapter in Methods in Molecular Biology.

License: This is an open access protocol distributed under the terms of the [Creative Commons Attribution License](#), which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working

Here, we describe an easy-to-use, detailed bench protocol for application of TT-seq, including in vitro transcribed RNA spike-in controls that enable normalization across samples, estimation of the amount of cross-contamination by non-labeled RNA, and a correction for antisense artifacts. This manuscript will be published as a chapter in Methods in Molecular Biology.

Created: June 07, 2019

Last Modified: June 13, 2019

Protocol Integer ID: 24217

Keywords: Transient transcriptome sequencing (TT-seq), nascent RNA, 4-thiouridine (4sU), RNA fragmentation, spike-ins, RNA synthesis, RNA processing, enhancer RNA (eRNA), transcription unit (TU) annotation, productive initiation rates, enhancer transcription transcriptome analysis by rna, transient transcriptome, rnas such as enhancer, labeled rna, including enhancer transcription transcriptome analysis, rna, rna metabolism, rna spike, synthesized rna fragment, state abundance of cellular rna, transcription regulation, rna degradation, higher sensitivity than rna, cellular rna, transcription response, rna synthesis, pulse with an rna fragmentation step, mechanistic studies of transcription regulation, associated rna, wide rna synthesis, rna fragmentation step, rapid changes in gene activity, genome, sequencing data, transcript, human genome, large genomes such as the human genome, large genome, thiouridine, gene activity, enhancer

Abstract

Transcriptome analysis by RNA sequencing (RNA-seq) measures the steady-state abundance of cellular RNA, which is a result of the interplay of RNA synthesis and RNA degradation. In order to measure RNA synthesis, RNA can be labeled with 4-thiouridine (4sU) in cells, purified and sequenced (4sU-seq). Although 4sU-seq has a higher sensitivity than RNA-seq, it is not sensitive enough to reliably detect short-lived (transient) RNAs such as enhancer, antisense, and promoter-associated RNAs synthesized from large genomes such as the human genome. This is because when the 4sU labeling time is less than 30 min only a short 3'-region of transcripts is labeled, and a long pre-existing unlabeled 5' region leads to a 5'-bias in the sequencing data. Transient transcriptome sequencing (TT-seq) overcomes this limitation by combining a short 4sU labeling pulse with an RNA fragmentation step. The labeled, newly synthesized RNA fragments are purified and sequenced, resulting in a very low fraction of contaminating non-labeled RNA. TT-seq is easy to use and includes RNA spike-in controls for global normalization between datasets from different samples. TT-seq enables studies of the kinetics of RNA metabolism, and mechanistic studies of transcription regulation. Also, TT-seq is ideally suited to monitor rapid changes in gene activity as well as the dynamics of enhancer landscapes during transcription responses.



Materials

MATERIALS

- ✕ MEGAscript® T7 Transcription Kit **Thermo Scientific Catalog #AM1334**
- ✕ KOD Hot Start DNA Polymerase **Merck MilliporeSigma (Sigma-Aldrich) Catalog #71086-3**
- ✕ Qubit RNA HS Assay Kit **Thermo Fisher Scientific Catalog #Q32852**
- ✕ Qubit assay tubes **Thermo Fisher Scientific Catalog #Q32856**
- ✕ ERCC RNA Spike-In Mix or order custom-made synthetic sequences **Thermo Fisher Scientific Catalog #4456740**
- ✕ Transcriptor First Strand cDNA Synthesis Kit **Roche Catalog #04379012001**
- ✕ QIAquick PCR purification columns **Qiagen Catalog #28104**
- ✕ 4-Thio-UTP **Jena Bioscience Catalog #NU-1156S**
- ✕ RNase-free AMPure XP beads **Beckman Coulter**
- ✕ 4-thiouridine (4sU) **Merck MilliporeSigma (Sigma-Aldrich) Catalog #T4509**
- ✕ Cell scraper **Corning Catalog #3011**
- ✕ Chloroform **Merck MilliporeSigma (Sigma-Aldrich) Catalog #372978**
- ✕ Ethanol **Merck Millipore (EMD Millipore) Catalog #100983**
- ✕ Isopropanol **Merck Millipore (EMD Millipore) Catalog #109634**
- ✕ 1.5 mL Bioruptor Plus TPX micro tubes **Diagenode Catalog #C30010010-300**
- ✕ Screw Cap Micro Tube 2 mL polypropylene (PP) **Sarstedt Catalog #72.694.005**
- ✕ EZ-Link Biotin-HPDP **Thermo Fisher Scientific Catalog #21341**
- ✕ 15 mL MaXtract High Density tubes **Qiagen Catalog #129065**
- ✕ μMACS Streptavidin Kit **Miltenyi Biotec Catalog #130-074-101**
- ✕ DL-dithiothreitol (DTT) **Merck MilliporeSigma (Sigma-Aldrich) Catalog #43815**
- ✕ miRNeasy Micro Kit **Qiagen Catalog #217084**
- ✕ RNase-Free DNase Set **Qiagen Catalog #79254**
- ✕ Sodium Acetate Solution (3 M) pH 5.2 **Thermo Fisher Scientific Catalog #R1181**
- ✕ NaCl (5 M) RNase-free **Thermo Fisher Scientific Catalog #AM9759**
- ✕ Bioanalyzer RNA 6000 Nano Kit **Agilent Technologies Catalog #5067**
- ✕ Ovation Universal RNA-Seq System (NuGEN) **Tecan**
- ✕ AnyDeplete (formerly InDA-C) **Tecan**
- ✕ KAPA Library Quantification Kit **Kapa Biosystems**




 Bioanalyzer DNA 1000 Chip **Agilent Technologies Catalog #5067**

All materials, consumables and chemicals must be sterile, RNase-free, molecular biology grade.

It is essential to use RNase-free equipment.



Troubleshooting

Buffers and Stock Solutions

- 1 Prepare [M] 50 mM **4-thiouridine (4sU) stock solution**. Dissolve 4sU in sterile RNase-free PBS. Store in small aliquots at  -20 °C .

Note

Thaw 4sU only once, and use immediately. As 4sU is photoactivatable and crosslinks to proteins at 365 nm, avoid light sources that emit this wavelength. The incorporation of 4sU can be validated by **dot blot** (see e.g. [Radle et al. 2013](#)).

- 2 Prepare **EZ-link HPDP-biotin stock solution**. EZ-link HPDP-biotin is pyridyldithiol-activated and allows thiol-specific biotinylation of labeled RNA. Dissolve in dimethylformamide (DMF) to [M] 1 mg/mL , mix thoroughly and incubate at  37 °C until it is completely dissolved. Repeat mixing if needed. Store in small aliquots in 2 mL PP micro tubes at  -20 °C .

Note

Please refer to safety data sheet for hazardous identification of DMF. Always wear gloves and eye protection. Avoid contact with skin or clothing. Use in a chemical hood. Avoid breathing vapor. DMF should not get in contact with incompatible plastic materials. Eluted plastic might be carried along and causes substantial loss of labeled RNA.

Note

Regarding the use of MTS-biotin ([Duffy et al. 2015](#)) in replacement of HPDP-biotin. We performed extensive control experiments to evaluate the described use of MTS-biotin in replacement of HPDP-biotin for our TT-seq protocol. For instance, we used 4sU-free total cellular RNA spiked-in with 0.1 % of 4sU labeled spike-ins, to assess the specificity of both biotins. When using MTS-biotin we found high levels of cross-contamination in the 4sU-pulldown fraction with unlabeled cellular RNA. This is in agreement with [Marzi and Nicassio 2018](#) who detected 10-fold higher background levels for MTS-biotin compared to HPDP-biotin. Recently an improved MTS-biotin protocol including optimized biotin chemistry (MTS-resin) was developed ([Duffy et al. 2018](#)). As we have not yet tested this improved biotinylation protocol, we recommend to carry out careful control experiments before using this alternative for TT-seq.

- 3 Prepare **10x biotinylation buffer** containing [M] 100 mM Tris HCl pH 7.4 and [M] 10 mM EDTA pH 8.0. Store in small aliquots at 4 °C .
- 4 Prepare **µMACS wash buffer** containing [M] 100 mM Tris HCl pH 7.4, [M] 10 mM EDTA pH 8.0, [M] 1 M NaCl, [M] 0.1 % (vol/vol) Tween20.
- 5 Prepare [M] 1 M **DL-dithiothreitol (DTT)** in RNase-free H₂O. Store in small aliquots at -20 °C . Thaw only once, and dilute to [M] 100 mM before use.
- 6 Prepare miRNeasy Micro Kit **buffer RWT with isopropanol** instead of ethanol (see manufacturer's instructions for "DNase digestion for samples containing <1 µg total RNA approximately").

Spike-in Pool Preparation (based on Schwalb et al. 2016)

- 7 Six synthetic RNA spike-in controls (three unlabeled and three 4sU labeled spike-ins) were established for validation of labeled RNA enrichment, global normalization and for estimating possible cross-contamination from unlabeled RNA fragments. The spike-ins are derived from selected RNAs of the ERCC RNA Spike-in Mix ([Schwalb et al. 2016](#)). We chose six spike-ins of about 1,000 nt length, a GC content between 40 to 60 % and similar uridine content. The IVT simulates the *in vivo* labeling of the cells, assuming that one out of ten uridine bases is substituted with 4sU. If polyadenylated RNA spike-ins are required, add a poly(A) tailing step after PCR amplification, or perform the IVT directly from custom-made DNA sequences containing poly(A) tails.

Selected RNA spike-ins derived from the ERCC RNA Spike-in Mix.



ERC C ID	Len gth (nt)	%U TP	%4s UTP	%G C	Nam e (TT- seq)
00043	985	90	10	34	Spik e-in 1
00170	949	100	0	35	Spik e-in 2
00136	1,014	90	10	43	Spik e-in 3
00145	1,015	100	0	46	Spik e-in 4



000 92	1,07 9	90	10	52	Spik e-in 5
000 02	1,03 7	100	0	53	Spik e-in 6

Note

Steps 8-12 can be omitted by ordering custom-made DNA sequences.

- 8 Perform first strand cDNA synthesis using the Transcriptor First Strand cDNA Synthesis Kit with Anchored-oligo (dT) primers. Follow manufacturer's instructions, use  1 μ L ERCC RNA Spike-in Mix.
- 9 Amplify specific spike-ins from  1 μ L of **1:4 diluted** cDNA using KOD Hot Start DNA Polymerase following manufacturer's instructions (30 cycles).

Primer sequences to amplify the cDNA template for IVT reaction of RNA spike-ins.


Prim er nam e (TT- seq)	Seq uen ce 5'>3 '	Ann eali ng tem pera ture (°C)
Spik e-in 1 forw ard	TAA TAC GAC TCA CTA TAG GGT GCT TTA ACA AGA GGA AAT TGT GT	53
Spik e-in 1 reve rse	CCA TCT TGT TTA TAA AAT CCT	53







		AAT TAC TC	
	Spik e-in 2 forw ard	TAA TAC GAC TCA CTA TAG GGG GCA CAA GTT GCT GAA GTT GC	55
	Spik e-in 2 reve rse	TCT GCT GTA ATC TCA GCT CC	55
	Spik e-in 3 forw ard	TAA TAC GAC TCA CTA TAG GGT TTC GAC GTT TTG AAG GAG GG	53
	Spik e-in 3 reve rse	GTA CCC GGG AAA ATC CTA GTT C	53
	Spik e-in 4 forw ard	TAA TAC GAC TCA CTA TAG GGA CTG TCC TTT CAT CCA	55



		TAA GCG G	
	Spik e-in 4 reve rse	CGC ACG CCG AAT GAT GAA ACG	55
	Spik e-in 5 forw ard	TAA TAC GAC TCA CTA TAG GGG ATG TCC TTG GAC GGG GT	55
	Spik e-in 5 reve rse	GCT TTC GGA GCA AAT CGC G	55
	Spik e-in 6 forw ard	TAA TAC GAC TCA CTA TAG GGC CAG ATT ACT TCC ATT TCC GCC	55
	Spik e-in 6 reve rse	GGG TAA AAC GCA AGC ACC G	55

- 10 Purify PCR products with QIAquick PCR purification columns following manufacturer's instructions. Elute in  30 μL .
- 11 Control size and purity of PCR products by gel electrophoresis.

Note

Optional cDNA purification: if PCR products show contamination with smaller fragments, isolate the PCR product of the desired size by gel extraction (e.g. by QIAquick Gel Extraction Kit).
- 12 Verify sequence of PCR products by Sanger sequencing.
- 13 Use  0.5 μg PCR product (or, custom-made DNA) as input for *in vitro* transcription (IVT) using the MEGAscript T7 kit. Follow manufacturer's instructions, **except for IVT of labeled RNA spike-ins (referred to as 1, 3, 5) substitute**  10 % **of UTP with 4-Thio-UTP.**
- 14 Purify RNA spike-ins with RNase-free AMPure XP beads following manufacturer's instructions.
- 15 Use the Qubit HS RNA Kit and Agilent RNA 6000 Nano Kit for quantification and quality assessment.
- 16 For the final RNA spike-in pool containing equimolar amounts of all six RNA spike-ins, add each RNA spike-in to a final concentration of  1 $\text{ng}/\mu\text{L}$.
- 17 Assess the actual concentration of your RNA spike-in pool by Qubit HS RNA Kit and use this concentration as your working concentration.
- 18 Store RNA spike-in pool in small, one-time use aliquots at  -80 $^{\circ}\text{C}$ (see **Step 25** for the required amount of spike-ins per sample).

Cell Treatment and 4sU Labeling



- 19 The required number of cells depends on the cell line under study. The exact cell count is required to calculate the corresponding amount of RNA spike-ins.

Note


Depending on cell type specific parameters (doubling time, transcriptional activity, and amount of cellular RNA), between 300 to 600 μg total RNA are needed to isolate sufficient amounts of labeled RNA ($> 50 \text{ ng}$). To establish a 4sU-labeling experiment, determine first how many cells are needed to yield 300 (or 600 μg) of total RNA and then, how much labeled RNA can be isolate from 300 μg (or 600 μg) input RNA. Based on these results, calculate the required number of cells. Typically, for 5 min of 4sU labeling the required number of cells is $1.5 \text{ to } 5 \times 10^7$. At the time of labeling cells should still be in their exponential growth phase to ensure high transcriptional activity. Therefore, we label cells at around 70 % confluence.


- 20 Optional: add treatment prior to 4sU labeling.





Note

Labeling of control and treated cells: when comparing TT-seq of control and manipulated cells it is critical that cell densities and labeling times are kept consistent for comparable 4sU uptake and incorporation.

21 Labeling of Adherent Cells

- 21.1 24-48 h before the experiment, plate the required number of cells in 15 cm dishes ( 20 mL culture medium). Seed 1-2 additional plates for cell counting.

- 21.2  00:30:00 before labeling thaw 4sU stock solution on ice and count cells.



- 21.3 For 4sU labeling, incubate cells with a final concentration of  500 μM 4sU at  37 $^{\circ}\text{C}$,  5 % CO_2 for exactly  00:05:00 .

**Note**

4sU labeling of adherent cells: just before labeling, pipet the required amount of 4sU for each plate into a sterile 50 mL tube. Remove half of the culture medium from each plate (it is important to leave some volume behind to not stress the cells) and add to the 50 mL 4sU-tube, mix and immediately pour back. Do not handle more than three plates in parallel.

Note


4sU concentration and labeling time can be adjusted to yield more labeled RNA. However, it is important to balance labeling concentration and time to avoid possible inhibition of rRNA synthesis ([Burger et al. 2013](#)) and cell toxicity.

- 21.4 After  00:05:00 quickly remove culture medium and add  4.5 mL of TRIzol lysis reagent.

Safety information

Please refer to safety data sheet for hazardous identification of TRIzol lysis reagent. Always wear gloves and eye protection. Avoid contact with skin or clothing. Use in a chemical hood. Avoid breathing vapor.

- 21.5 "Wash" cells off the plate by pipetting up and down. If cells are very adherent, use a TRIzol compatible cell scraper.

- 21.6 Transfer cell lysate to 15 mL polypropylene (PP) centrifuge tube and incubate up to  00:05:00 .

Note

Use centrifuge tubes for high speed ($\geq 13,000$ g) centrifugation.

**Note**

If several plates are labeled simultaneously, two lysates from the same condition can be pooled into one PP tube (minimizes the number of tubes).

21.7 Optional: store lysates at -80 °C .

22 Labeling of Suspension Cells

22.1 Dilute cells 48 h before the labeling experiment and exchange growth medium one day before labeling.

22.2 00:30:00 before labeling thaw 4sU stock solution on ice and count cells.

22.3 Add 500 µL of 4sU stock solution to cells in 50 mL of growth medium to a final concentration of 500 µM , and incubate at 37 °C , 5 % CO₂.

22.4 Exactly after 00:05:00 of labeling, centrifuge at 37 °C and 500-1,500 x g for 00:02:00 . Discard supernatant by decanting.

22.5 Add 5 mL of TRIzol lysis reagent to cell pellet. Vortex until no cells are visible (00:00:30).

22.6 Incubate for 00:05:00 . Transfer to 15 mL PP centrifuge tubes.

Note

Use centrifuge tubes for high speed (≥13,000 x g) centrifugation.

22.7 Optional: store lysates at -80 °C .



RNA Spike-in Pool Addition and Total RNA Extraction

23 If lysates were frozen, thaw quickly at 65 °C (water bath), then cool on ice for 00:05:00 .

24 Thaw RNA Spike-in mix at 65 °C for 00:02:00 , cool on ice for 00:01:00 and mix gently by pipetting.

25 Add 2.4 ng spike-in mix per 10^6 cells to TRIzol cell lysate.

Note

RNA spike-in addition to cell lysate: the amount of RNA spike-ins depends on the complexity and concentration of the final sample, but also on how deep the library is sequenced. In general, a balance between detecting the spike-ins and not having too many sequencing reads for spike-ins is recommended.

26 Vortex gently and incubate for 00:05:00 .

27 Add 0.2 mL of chloroform **per** 1 mL of TRIzol lysis reagent.

28 Shake vigorously for 00:00:15 and incubate for 00:03:00 .

29 Centrifuge at 4 °C and 13000 x g for 00:15:00 .

30 Carefully transfer upper, aqueous phase into new 15 mL centrifuge tube.

31 Add an **equal volume** of isopropanol to precipitate RNA, vortex gently.

32 Incubate for 00:10:00 .

33 Centrifuged at 4 °C and 13000 x g for 00:10:00 .



34 Wash RNA pellet twice, first using an **equal volume**, then 1 mL of [M] 75 % ethanol. Spin in-between at 4 °C and 13000 x g for 00:10:00 .

35 Remove supernatant with 1 mL pipette. Spin down briefly and use 200 µL pipette to remove remaining ethanol. Eventually, spin down again and use 10 µL pipette.

36 Dissolve pellet in **200-1,000 µL** H₂O (aim for a final concentration of ≥ 750 ng/µL).

37 Transfer RNA to 1.5 mL tube.

Note

Optional: pool samples from the same condition into one tube.

38 Determine concentration and purity by NanoDrop spectrophotometer; 260/280 value should be >2.

39 **Save** 1 µL of total RNA for quality control on Agilent Bioanalyzer RNA 6000 Nano Chip (**Step 45**).

40 Optional: store at -80 °C .

Mild RNA Fragmentation (based on Schwalb et al. 2016)

41 Cool Bioruptor Plus to 4 °C before use. Transfer 300 µg of total RNA to 1.5 mL Bioruptor Plus TPX microtubes, adjust to [M] 750 ng/µL .

Note

If processing 600 µg RNA: use two 1.5 mL Bioruptor Plus TPX microtubes (300 µg each).

Note

RNA fragmentation using Covaris S220: transfer two-times $150\ \mu\text{g}$ of total RNA (each in a final volume of $130\ \mu\text{L}$) to $130\ \mu\text{L}$ microTUBE AFA Fiber Snap-Cap tubes. Use the following settings: water level 12, temperature $7\ ^\circ\text{C}$, peak incident power 100 W, duty factor 1 %, cycles per burst 200, treatment time 10-60 sec.



















- 42 Fill empty positions in the tube holder with tubes containing $400\ \mu\text{L}$ water.
- 43 Settings: 1 cycle, 30 sec ON, 30 sec OFF at HIGH power.
- 44 Transfer (optional: pool) samples to 2 mL PP microtubes. Continue immediately with the biotinylation reaction.
- 45 After fragmentation, use $1\ \mu\text{L}$ of total fragmented RNA for quality control on Agilent Bioanalyzer RNA 6000 Nano Chip and compare to $1\ \mu\text{L}$ of total RNA. For expected results see **Step 94**.

Biotinylation of 4sU Labeled RNA (based on Dölken et al. 2008)






- 46 Denature total fragmented RNA at $65\ ^\circ\text{C}$ for 00:10:00, then place on ice for 00:05:00.
- 47 **Save** $5\ \mu\text{L}$ of total fragmented RNA for DNase I digest (**Step 75**).
- 48 Split remaining total fragmented RNA in **two** 2 mL PP microtubes ($150\ \mu\text{g}$ /reaction) and process in parallel in **Steps 49-53**.

Note



If processing $600\ \mu\text{g}$ RNA: split total fragmented RNA in **four** 2 mL PP microtubes ($150\ \mu\text{g}$ /reaction) and process in parallel (**Steps 49-53**).

- 49 Add water **up to**  700 μL .
- 50 Prepare **biotin master mix** in the stated order:  100 μL of 10x biotinylation buffer,  200 μL of EZ-link HPDP-Biotin stock solution.
- 51 Add  300 μL biotin master mix to each sample and mix immediately.
- 52 Incubate in the dark with rotation for  02:00:00 .
- 53 Shortly before use, prepare 15 mL MaXtract High Density tubes following the manufacturer's instruction.
- 54 Transfer biotin-RNA mix to MaXtract High Density tubes, **pool reactions from the same condition**.
- 55 Add an **equal volume** of chloroform. Mix vigorously for  00:00:15 and incubate for  00:03:00 .
- 56 Centrifuge at  1500 x g for  00:05:00 .
- 57 Transfer upper phase into 15 mL PP centrifuge tube.
- 58 For RNA precipitation, add **1/10 volume** of  5 M NaCl and an **equal volume** of isopropanol. Vortex gently.
- 59 Centrifuge at  4 $^{\circ}\text{C}$ and  13000 x g for  00:30:00 . Remove supernatant.
- 60 Wash RNA pellet twice, first using an **equal volume**, then  1 mL of  75 % ethanol. Spin in-between at  4 $^{\circ}\text{C}$ and  13000 x g for  00:10:00 .
- 61 Remove supernatant with 1 mL pipette. Spin down briefly and use 200 μL pipette to remove remaining ethanol. Optionally, spin down again and use 10 μL pipette.


















- 62 Resuspend RNA in  100 μL H_2O per  300 μg biotinylation reaction: chill on ice  00:10:00 , then heat at  65 $^{\circ}\text{C}$ for  00:10:00 , put on ice and carefully resuspend by pipetting. Transfer to 2 mL LoBind tubes.
- 63 Continue immediately with 4sU pull-down.

Pull-down of 4sU Labeled RNA Using Streptavidin-Beads

- 64 Use one μMACS column per  300 μg ( 200 μL) RNA.

Note

If processing  600 μg RNA: use **two** μMACS columns with  300 μg ( 200 μL) RNA each.



- 65 Heat μMACS wash buffer ( 3 mL / μMACS column) to  65 $^{\circ}\text{C}$.
- 66 Add  100 μL of μMACS streptavidin beads to  200 μL RNA.
- 67 Incubate at  4 $^{\circ}\text{C}$ with rotation for  00:15:00 .
- 68 In the meantime, equilibrate μMACS columns with  100 μL of nucleic acids equilibration buffer (equilibrate at RT  00:10:00 before use).
- 69 Transfer RNA-bead-mix to the μMACS column, **collect the flow-through** in LoBind tubes and reapply to the μMACS column. Discard flow-through.
- 70 Wash 3-times with  900 μL of **μMACS wash buffer** ( 65 $^{\circ}\text{C}$). Discard flow-through.
- 71 Wash 3-times with  900 μL of **μMACS wash buffer** ( Room temperature). Discard flow-through.

72 Place 1.5 ml LoBind tubes underneath the columns.

73 Elute labeled RNA in  100 μ L of [M] 100 mM DTT.


74 After  00:05:00 elute in additional  100 μ L of [M] 100 mM DTT.

Final RNA Clean-up and DNase Digest

75 Prepare  1 μ g total fragmented RNA (**Step 47**). Mix samples thoroughly by shaking for  00:00:15 .

Total fragmented RNA (1 μ g)	200 μ L
3 M NaAc pH 5.2	15 μ L
100 % ethanol	300 μ L

Note


From here on use low binding pipette tips. Process labeled RNA and  1 μ g of total fragmented RNA in parallel.



76 Prepare labeled RNA (**Step 74**). Mix samples thoroughly by shaking for  00:00:15 .




4sU label ed RNA	200 μL
100 % etha nol	300 μL



77 Transfer samples onto miRNeasy MinElute spin column in a 2 mL collection tube.



Note

If processing labeled RNA isolated from  600 μg total fragmented RNA: pool samples from the same condition onto **one** RNeasy MinElute spin column by repeating **Step 78**.


78 Centrifuge at  8000 x g for  00:00:15 . Reload flow-through.

79 Wash with  350 μL of RWT buffer by centrifugation at  8000 x g for  00:00:30 .















80 Prepare DNase mix:  70 μL RDD buffer and  10 μL RNase-free DNase I, mix by pipetting or inverting.

81 Add  80 μL DNase master mix to each column and incubate for  00:15:00 .

82 Add  500 μL of RWT buffer.

83 Centrifuge at  8000 x g for  00:00:30 . **Reload flow-through.**




- 84 Centrifuge at  8000 x g for  00:00:30 . Discard flow-through.
- 85 Add  500 µL of RPE buffer.
- 86 Centrifuge at  8000 x g for  00:00:30 .
- 87 Place column into a new 2 mL collection tube.
- 88 Wash with  500 µL of  80 % ethanol. Centrifuge at  8000 x g for  00:02:00 . Place column into new 2 mL collection tube.
- 89 To dry the membrane, open the lid and centrifuge at full speed for  00:05:00 .
- 90 Place column into new 1.5 mL LoBind tube.
- 91 Elute with  15 µL of nuclease free H₂O (not DEPC treated) by centrifugation at full speed for  00:01:00 . Reload flow-through for a second elution. If a low labeled RNA yield is expected: use  11 µL of H₂O and incubate  00:01:00 before centrifugation.
- 92 Transfer RNA to a new 1.5 mL LoBind tube.
- 93 Measure RNA concentration with Qubit RNA HS Kit and analyze RNA integrity on Agilent Bioanalyzer RNA 6000 Pico Chip.

Expected Result

94 **Examples of RNA integrity profiles of total, total fragmented and labeled RNA isolated from human cell lines.**

Expected result

Total fragmented RNA should be in a range between 0.2 and 15 kbp. Fragmentation efficiency might differ for RNA from another organisms. Thus, it is recommended to perform initial trials with your cell lines. Be aware that after sonication it is expected that the RIN value drops since rRNA is also fragmented.



Agilent Bioanalyzer profiles of total RNA (a) and total fragmented RNA (b) on a RNA 6000 Nano Chip. Agilent Bioanalyzer profiles of labeled RNA on a RNA 6000 Pico Chip from a cell line with high (c) and low (d) amounts of labeled RNA.

95 **Highly recommended: validation of labeled RNA enrichment by reverse transcription PCR (RT-qPCR) of RNA spike-ins.**

Note

Control of labeled RNA enrichment by RT-qPCR. Prepare cDNA from 400 ng total fragmented RNA and 1 μ L labeled RNA, and perform RT-qPCR. Use primer pairs for RNA spike-ins to estimate labeled RNA enrichment, and (optional) for endogenous model genes of your choice to measure the intron enrichment.

Primer sequences for RT-qPCR of RNA spike-ins to control enrichment of labeled RNA.



	Prim er nam e (TT- seq)	Seq uen ce 5'>3 '	Ann eali ng tem pera ture	Amp lico n size (bp)
	Spik e-in 1 forw ard	ACA ATT CCA AAT AGC GAC CAC ATC A	59	150
	Spik e-in 1 reve rse	TAC CTC AAC CCT TCC AGT GTC TAA G	58	
	Spik e-in 2 forw ard	AGA CTG GCA TTC CCG TGA TA	57	97
	Spik e-in 2 reve rse	GCT AAA ACC CCT GCC TGC AA	60	
	Spik e-in 3 forw ard	CCG AGT TCG CCT TAC TGC TC	60	95
	Spik e-in 3 reve rse	AAT CGA TCG GAA TCA CGC CG	60	
	Spik e-in 4	CAT AAG CGG	59	103






	forw ard	AGA AAG AGG GAA TGA C		
	Spik e-in 4 reve rse	GCT AAA TAG AGA GCA TCC ACA CCT C	58	
	Spik e-in 5 forw ard	CGT TAA TGC AGA GGC TAA GGA CAA T	59	103
	Spik e-in 5 reve rse	GAT CGT TAC AAA CCC ACT ACG TGT C	59	
	Spik e-in 6 forw ard	GTC CTG ATT TAC TGG ACT CGC AAC	58	118
	Spik e-in 6 reve rse	TCT GTA TAA GGT GAT CGC AGG TTG T	59	

Expected result

For total fragmented RNA, the Ct values of labeled and unlabeled RNA spike-ins are very similar. Labeled RNA shows a Ct value difference of 6-10 for labeled and unlabeled RNA spike-ins. For the selected model gene, intron levels should be enriched in labeled RNA compared to total fragmented RNA.

Library Preparation




- 96 We recommend using  100 ng (at least  50 ng) labeled RNA and  100 ng total fragmented RNA as library input.

Note


We recommend using the Ovation Universal RNA-Seq System (NuGEN). The option of using only random primers for cDNA synthesis omits the 3' bias generated by poly-(dT) primers. Also, the NuGEN kit depletes ribosomal RNA by sequence-specific probes (AnyDeplete technology, formerly known as InDA-C).





Note

Total fragmented RNA samples are needed to estimate RNA half-lives and correct the cross-contamination using RNA spike-ins. If the cross-contamination rate is similar across your libraries (which can be estimated from the RNA spike-ins), labeled RNA might be sufficient.

- 97 For 'First Strand Primer Pre-mix Preparation', use only Random primer mix. Substitute poly-d(T) primers with  0.4 μ L H_2O .
- 98 Follow the User guide's instruction from 'First Strand Synthesis Using DNase-treated RNA' to 'Second Strand cDNA Synthesis'.
- 99 For 'cDNA fragmentation' (200-400 bp) using a Bioruptor Plus device: Aliquot  100 μ L cDNA in Qubit assay tubes. Fill up empty positions in the tube holder with tubes containing  100 μ L water. Do 15 cycles, 30 sec ON, 30 sec OFF at LOW power. Spin down samples and add another 10 cycles. If the Bioruptor is not connected to an automated cooling system. Cool the water bath with ice in-between the 15 and 10 cycles.

Note

cDNA fragmentation using Covaris S220 (200-400 bp): transfer cDNA to 130 μ L microTUBE AFA Fiber Snap-Cap tube. Use the following settings: water level 12, temperature  7 °C, peak incident power 145 W, duty factor 10 %, cycles per burst 200, treatment time 50-180 sec.

- 100 Follow the User guide's instruction from 'cDNA Concentration After Fragmentation' to 'Adaptor Cleavage'.
- 101 Before 'PCR amplification': To avoid over-amplification determine the precise number of PCR cycles by the KAPA HIFI Library Amp Real Time kit following manufacturer's instructions. As input, use  4.2 μ L (~10 %) of the library,  5 μ L of 2x Kapa HiFi Hot Start Master Mix and  0.8 μ L Amplification Primer Mix P2 (NuGEN).
- 102 For 'PCR amplification' of the remaining  45 μ L of library use the determined number of PCR cycles and follow the User guide's instructions for amplification as described in the Appendix 'Using qPCR to determine the Number of PCR Cycles'.
- 103 Proceed from 'Bead Purification of the Amplified Material' to 'Quantitative and Qualitative Assessment of the Library'.
- 104 Assess the quality of the library on Bioanalyzer DNA 1000 Chip and send to sequencing service providers for high throughput sequencing.

Paired-end Illumina Sequencing

- 105 **Universal RNA-Seq with NuQuant** The read length for human transcriptomes should be between 35 to 150 bp depending on the desired application. For alternative splicing detection, longer reads are recommended, i.e. 150 bp paired-end sequencing. Recommended coverage: in general, 25 to 50 million reads per sample are sufficient for an initial analysis of highly expressed transcripts. 100 million reads is the required sequencing depth for annotation of enhancer RNAs or antisense RNAs in TT-seq (labeled RNA) samples (see [Deveson et al. 2017](#) for review). If the focus of a study is on newly synthesized RNA fragments, total fragmented RNA-seq libraries can be sequenced with a lower coverage, i.e. 30 million reads. If a study aims to study RNA stability, TT-seq and total fragmented RNA-seq libraries should be sequenced at similar coverage.

Computational analysis



- 106 The bioinformatics workflow used to analyze TT-seq data is presented in Villamil et al. 2019. The pre-print describe pre-processing steps, including a reliable and robust normalization strategy, and several downstream analysis tools that enable the user to quantify RNA synthesis, splicing and degradation activities.